

IVI.NET driver history for the R&S RTM2000 Digital Oscilloscopes

Products:

| R&S® RTM20xx



Driver history for IVI.NET - C#, Visual Basic .NET, etc.

Table of Contents

1	Supported Instruments.....	3
2	IVI.NET driver history.....	4

1 Supported Instruments

In the following table the supported R&S instruments and firmware versions are listed:

Which instruments are supported?		
Current revision of instrument driver supports these instruments and firmware versions:		
Instrument	Supported Firmware	Remarks
RTM20xx	6.010	

2 IVI.NET driver history

RsRtm20xx Instrument Driver		
Driver history for C#, Visual Basic .NET		
Revision	Date	Note
1.5.0	01/2017	<ul style="list-style-type: none"> * New properties/methods: - RsRtm20xx.UtilityFunctions.WriteCommandWithOPCSync() - RsRtm20xx.UtilityFunctions.QueryWithOPCSync() - RsRtm20xx.UtilityFunctions.IDQueryResponse * Modified properties/methods: - RsRtm20xx.Measurements["M1"].ConfigureMeasurementSource() - SCPI command parameter corrected
1.4.1	04/2016	<ul style="list-style-type: none"> Modified properties/methods: - RsRtm20xx.WaveformAcquisition.Waveform.ReadWaveform() - replaced using RSRTM20XX_ATTR_RUN_SINGLE with RSRTM20XX_ATTR_RUN_SINGLE_WAIT_FOR_OPC
1.4.0	03/2016	<ul style="list-style-type: none"> * Support for firmware 5.851 * New Subsystems - Spectrum Analysis - Digital Voltmeter and Counter * New properties/methods: - RsRtm20xx.Acquisition.TimestampsFilename - RsRtm20xx.Acquisition.TimestampsSave - RsRtm20xx.Label.Bus.Enabled - RsRtm20xx.Label.Bus.LabelName - RsRtm20xx.Channel.AllOff - RsRtm20xx.Channel.AllOn - RsRtm20xx.Trigger.ExternalTriggerTermination - RsRtm20xx.Trigger.ExternalTriggerOverload - RsRtm20xx.Trigger.HysteresisALevel - RsRtm20xx.Trigger.HysteresisBLevel - RsRtm20xx.WaveformAcquisition.EnvelopeWaveform.DataPoints - - RsRtm20xx.Measurements.AutomaticMeasurementsStatistics.ExportAutomaticMeasurements.MeasurementsName - RsRtm20xx.Measurements.AutomaticMeasurementsStatistics.ExportAutomaticMeasurements.Save - RsRtm20xx.Measurements.AutomaticMeasurementsStatistics.ExportAutomaticMeasurements.AllName - RsRtm20xx.Measurements.AutomaticMeasurementsStatistics.ExportAutomaticMeasurements.AllSave - RsRtm20xx.Mathematics.DataPoints - RsRtm20xx.ReferenceWaveforms.DataPoints - RsRtm20xx.Protocols.ParallelBus.ParallelBusClocked.Source - RsRtm20xx.Protocols.ParallelBus.ParallelBusClocked.ChipSelectEnabled - RsRtm20xx.Protocols.ParallelBus.ParallelBusClocked.ChipSelectSource - RsRtm20xx.PowerAnalysis.CurrentHarmonicsMeasurement.CurrentHarmonicsExport.ExportName - RsRtm20xx.PowerAnalysis.CurrentHarmonicsMeasurement.CurrentHarmonicsExport.Save - RsRtm20xx.SpectrumAnalysis.Enable

RsRtm20xx Instrument Driver		
Driver history for C#, Visual Basic .NET		
Revision	Date	Note
		<ul style="list-style-type: none"> - RsRtm20xx.SpectrumAnalysis.Source - RsRtm20xx.SpectrumAnalysis.FrequencyDomain.AverageComplete - RsRtm20xx.SpectrumAnalysis.FrequencyDomain.AverageCount - RsRtm20xx.SpectrumAnalysis.FrequencyDomain.MagnitudeScale - RsRtm20xx.SpectrumAnalysis.FrequencyDomain.Position - RsRtm20xx.SpectrumAnalysis.FrequencyDomain.Reset - RsRtm20xx.SpectrumAnalysis.FrequencyDomain.Scale - RsRtm20xx.SpectrumAnalysis.FrequencyDomain.WindowType - RsRtm20xx.SpectrumAnalysis.FrequencyDomain.Start - RsRtm20xx.SpectrumAnalysis.FrequencyDomain.Stop - RsRtm20xx.SpectrumAnalysis.FrequencyDomain.Center - RsRtm20xx.SpectrumAnalysis.FrequencyDomain.Span - RsRtm20xx.SpectrumAnalysis.FrequencyDomain.BandwidthAuto - RsRtm20xx.SpectrumAnalysis.FrequencyDomain.BandwidthRatio - RsRtm20xx.SpectrumAnalysis.FrequencyDomain.BandwidthResolution - RsRtm20xx.SpectrumAnalysis.Spectrogram.Reset - RsRtm20xx.SpectrumAnalysis.Spectrogram.Scale - RsRtm20xx.SpectrumAnalysis.Marker.Enable - RsRtm20xx.SpectrumAnalysis.Marker.Source - RsRtm20xx.SpectrumAnalysis.Marker.Display - RsRtm20xx.SpectrumAnalysis.Marker.SetupDistance - RsRtm20xx.SpectrumAnalysis.Marker.SetupExcursion - RsRtm20xx.SpectrumAnalysis.Marker.SetupMinimumLevel - RsRtm20xx.SpectrumAnalysis.Marker.SetupDetectionMode - RsRtm20xx.SpectrumAnalysis.Marker.SetupMaximumWidth - RsRtm20xx.SpectrumAnalysis.Marker.ReferenceMode - RsRtm20xx.SpectrumAnalysis.Marker.ReferenceFrequency - RsRtm20xx.SpectrumAnalysis.Marker.ReferenceSpan - RsRtm20xx.SpectrumAnalysis.Marker.ReferenceIndex - RsRtm20xx.SpectrumAnalysis.Marker.SpectrumMarkerTable.Enable - RsRtm20xx.SpectrumAnalysis.Marker.SpectrumMarkerTable.DetectedPeaks - RsRtm20xx.SpectrumAnalysis.Marker.SpectrumMarkerTable.ResultMode - RsRtm20xx.SpectrumAnalysis.Marker.SpectrumMarkerTable.Position - RsRtm20xx.SpectrumAnalysis.Display.MagnitudeMode - RsRtm20xx.SpectrumAnalysis.Display.MaximumLevel - RsRtm20xx.SpectrumAnalysis.Display.MinimumLevel - RsRtm20xx.SpectrumAnalysis.Display.ColorScheme - RsRtm20xx.SpectrumAnalysis.Display.SpectrogramColorScheme - RsRtm20xx.SpectrumAnalysis.Display.FrequencyDomainEnable - RsRtm20xx.SpectrumAnalysis.Display.SpectrogramEnable - RsRtm20xx.SpectrumAnalysis.Display.TimeDomainEnable

RsRtm20xx Instrument Driver		
Driver history for C#, Visual Basic .NET		
Revision	Date	Note
		<ul style="list-style-type: none"> - RsRtm20xx.SpectrumAnalysis.Waveform.Enable - RsRtm20xx.SpectrumAnalysis.Waveform.MinimumEnable - RsRtm20xx.SpectrumAnalysis.Waveform.MaximumEnable - RsRtm20xx.SpectrumAnalysis.Waveform.AverageEnable - RsRtm20xx.SpectrumAnalysis.TimeDomain.Position - RsRtm20xx.SpectrumAnalysis.TimeDomain.Range - RsRtm20xx.DigitalVoltmeterAndCounter.Enable - RsRtm20xx.DigitalVoltmeterAndCounter.Source - RsRtm20xx.DigitalVoltmeterAndCounter.Type - RsRtm20xx.DigitalVoltmeterAndCounter.Position - RsRtm20xx.DigitalVoltmeterAndCounter.Result - RsRtm20xx.DigitalVoltmeterAndCounter.ResultStatus - RsRtm20xx.DigitalVoltmeterAndCounter.Counter.Enable - RsRtm20xx.DigitalVoltmeterAndCounter.Counter.Frequency - RsRtm20xx.DigitalVoltmeterAndCounter.Counter.Period - RsRtm20xx.Display.DialogTransparency - RsRtm20xx.Display.History.Channel.AllDates - RsRtm20xx.Display.History.Channel.AllTimeDifferences - RsRtm20xx.Display.History.Channel.AllDaytimes - RsRtm20xx.Display.History.Digital.AllDates - RsRtm20xx.Display.History.Digital.AllTimeDifferences - RsRtm20xx.Display.History.Digital.AllDaytimes - RsRtm20xx.Display.History.Math.AllDates - RsRtm20xx.Display.History.Math.AllTimeDifferences - RsRtm20xx.Display.History.Math.AllDaytimes - RsRtm20xx.Display.History.Protocol.AllDates - RsRtm20xx.Display.History.Protocol.AllTimeDifferences - RsRtm20xx.Display.History.Protocol.AllDaytimes - RsRtm20xx.Display.History.Spectrum.CurrentAcquisition - RsRtm20xx.Display.History.Spectrum.Player - RsRtm20xx.Display.History.Spectrum.StartAcquisition - RsRtm20xx.Display.History.Spectrum.StopAcquisition - RsRtm20xx.Display.History.Spectrum.PlayAll - RsRtm20xx.Display.History.Spectrum.Speed - RsRtm20xx.Display.History.Spectrum.Repeat - RsRtm20xx.Display.History.Spectrum.ExportName - RsRtm20xx.Display.History.Spectrum.ExportSave - RsRtm20xx.UtilityFunctions.AddStreamLogger() - RsRtm20xx.UtilityFunctions.RemoveStreamLogger() - RsRtm20xx.UtilityFunctions.WriteStringToLog() - RsRtm20xx.UtilityFunctions.ReadToFileFromInstrument()

RsRtm20xx Instrument Driver		
Driver history for C#, Visual Basic .NET		
Revision	Date	Note
		<ul style="list-style-type: none"> - RsRtm20xx.UtilityFunctions.WriteFromFileToInstrument() - RsRtm20xx.UtilityFunctions.WriteToInstrument() - RsRtm20xx.UtilityFunctions.ReadInstrumentData() - RsRtm20xx.UtilityFunctions.ReadBinaryBlockToStream() - RsRtm20xx.UtilityFunctions.QueryBool() - RsRtm20xx.UtilityFunctions.QueryInt32() - RsRtm20xx.UtilityFunctions.QueryDouble() - RsRtm20xx.UtilityFunctions.QueryString() - RsRtm20xx.UtilityFunctions.Reset() - RsRtm20xx.UtilityFunctions.SelfTest() - RsRtm20xx.UtilityFunctions.ErrorMessage() - RsRtm20xx.UtilityFunctions.RevisionQuery() - RsRtm20xx.UtilityFunctions.Delay() - RsRtm20xx.UtilityFunctions.SystemPreset - RsRtm20xx.UtilityFunctions.Logging - RsRtm20xx.UtilityFunctions.OPCTimeout - RsRtm20xx.UtilityFunctions.QueryOPC - RsRtm20xx.UtilityFunctions.VisaTimeout - RsRtm20xx.UtilityFunctions.ProcessAllPreviousCommands - RsRtm20xx.UtilityFunctions.VisaManufacturer - RsRtm20xx.UtilityFunctions.ClearStatus - RsRtm20xx.UtilityFunctions.OptionChecking - RsRtm20xx.UtilityFunctions.ErrorQueryAll() <p>* Modified properties/methods:</p> <ul style="list-style-type: none"> - RsRtm20xx.HardcopyandPrinter.Print - Added WAIT after command <p>* Modified Range Tables:</p> <ul style="list-style-type: none"> - SampleMode.RealTime - RSRTM20XX_ATTR_SAMPLE_MODE Description changed ("Real Time", "") - SampleMode.EquivalentTime - RSRTM20XX_ATTR_SAMPLE_MODE Description changed ("Equivalent Time", "") - WfmArithmetics.Off - RSRTM20XX_ATTR_WAVEFORM_ACQUISITION_TYPE, RSRTM20XX_ATTR_MATH_ACQUISITION_TYPE Description changed ("Off", "") - WfmArithmetics.Envelope - RSRTM20XX_ATTR_WAVEFORM_ACQUISITION_TYPE, RSRTM20XX_ATTR_MATH_ACQUISITION_TYPE Description changed ("Envelope", "") - WfmArithmetics.Average - RSRTM20XX_ATTR_WAVEFORM_ACQUISITION_TYPE, RSRTM20XX_ATTR_MATH_ACQUISITION_TYPE Description changed ("Average", "") - WfmArithmetics.Smooth - RSRTM20XX_ATTR_WAVEFORM_ACQUISITION_TYPE,

RsRtm20xx Instrument Driver		
Driver history for C#, Visual Basic .NET		
Revision	Date	Note
		<p>RSRTM20XX_ATTR_MATH_ACQUISITION_TYPE Description changed ("Smooth", "")</p> <p>- WfmArithmetics.Filter - RSRTM20XX_ATTR_WAVEFORM_ACQUISITION_TYPE, RSRTM20XX_ATTR_MATH_ACQUISITION_TYPE Description changed ("Filter", "")</p> <p>- VerticalCoupling.AC - RSRTM20XX_ATTR_VERTICAL_COUPLING Description changed ("AC", "")</p> <p>- VerticalCoupling.DC - RSRTM20XX_ATTR_VERTICAL_COUPLING Description changed ("DC", "")</p> <p>- VerticalCoupling.DCLimit - RSRTM20XX_ATTR_VERTICAL_COUPLING Description changed ("DC Limit", "")</p> <p>- VerticalCoupling - RSRTM20XX_ATTR_VERTICAL_COUPLING New items: ACLimit, GND</p> <p>- ChannelBandwidthLimit.Full - RSRTM20XX_ATTR_CHANNEL_BANDWIDTH_LIMIT Description changed ("Full", "")</p> <p>- ChannelBandwidthLimit.Limit400MHz - RSRTM20XX_ATTR_CHANNEL_BANDWIDTH_LIMIT Description changed ("Limit 400MHz", "")</p> <p>- ChannelBandwidthLimit.Limit200MHz - RSRTM20XX_ATTR_CHANNEL_BANDWIDTH_LIMIT Description changed ("Limit 200MHz", "")</p> <p>- ChannelBandwidthLimit.Limit20MHz - RSRTM20XX_ATTR_CHANNEL_BANDWIDTH_LIMIT Description changed ("Limit 20MHz", "")</p> <p>- TriggerSource.Ch1 - RSRTM20XX_ATTR_TRIGGER_SOURCE_A, RSRTM20XX_ATTR_TRIGGER_SOURCE_B Description changed ("Channel 1", "")</p> <p>- TriggerSource.Ch2 - RSRTM20XX_ATTR_TRIGGER_SOURCE_A, RSRTM20XX_ATTR_TRIGGER_SOURCE_B Description changed ("Channel 2", "")</p> <p>- TriggerSource.Ch3 - RSRTM20XX_ATTR_TRIGGER_SOURCE_A, RSRTM20XX_ATTR_TRIGGER_SOURCE_B Description changed ("Channel 3", "")</p> <p>- TriggerSource.Ch4 - RSRTM20XX_ATTR_TRIGGER_SOURCE_A, RSRTM20XX_ATTR_TRIGGER_SOURCE_B Description changed ("Channel 4", "")</p> <p>- TriggerSource.External - RSRTM20XX_ATTR_TRIGGER_SOURCE_A, RSRTM20XX_ATTR_TRIGGER_SOURCE_B Description changed ("External Trigger Input", "")</p> <p>- TriggerSource.ACLine - RSRTM20XX_ATTR_TRIGGER_SOURCE_A, RSRTM20XX_ATTR_TRIGGER_SOURCE_B Description changed ("AC Line", "")</p> <p>- TriggerSource.SerialBus1 - RSRTM20XX_ATTR_TRIGGER_SOURCE_A, RSRTM20XX_ATTR_TRIGGER_SOURCE_B Description changed ("Serial Bus 1", "")</p> <p>- TriggerSource.SerialBus2 - RSRTM20XX_ATTR_TRIGGER_SOURCE_A,</p>

RsRtm20xx Instrument Driver		
Driver history for C#, Visual Basic .NET		
Revision	Date	Note
		RSRTM20XX_ATTR_TRIGGER_SOURCE_B Description changed ("Serial Bus 2", "") - TriggerSource.SerialBus3 - RSRTM20XX_ATTR_TRIGGER_SOURCE_A, RSRTM20XX_ATTR_TRIGGER_SOURCE_B Description changed ("Serial Bus 3", "") - TriggerSource.SerialBus4 - RSRTM20XX_ATTR_TRIGGER_SOURCE_A, RSRTM20XX_ATTR_TRIGGER_SOURCE_B Description changed ("Serial Bus 4", "") - TriggerSource.Digital0 - RSRTM20XX_ATTR_TRIGGER_SOURCE_A, RSRTM20XX_ATTR_TRIGGER_SOURCE_B Description changed ("Digital 0", "") - TriggerSource.Digital1 - RSRTM20XX_ATTR_TRIGGER_SOURCE_A, RSRTM20XX_ATTR_TRIGGER_SOURCE_B Description changed ("Digital 1", "") - TriggerSource.Digital2 - RSRTM20XX_ATTR_TRIGGER_SOURCE_A, RSRTM20XX_ATTR_TRIGGER_SOURCE_B Description changed ("Digital 2", "") - TriggerSource.Digital3 - RSRTM20XX_ATTR_TRIGGER_SOURCE_A, RSRTM20XX_ATTR_TRIGGER_SOURCE_B Description changed ("Digital 3", "") - TriggerSource.Digital4 - RSRTM20XX_ATTR_TRIGGER_SOURCE_A, RSRTM20XX_ATTR_TRIGGER_SOURCE_B Description changed ("Digital 4", "") - TriggerSource.Digital5 - RSRTM20XX_ATTR_TRIGGER_SOURCE_A, RSRTM20XX_ATTR_TRIGGER_SOURCE_B Description changed ("Digital 5", "") - TriggerSource.Digital6 - RSRTM20XX_ATTR_TRIGGER_SOURCE_A, RSRTM20XX_ATTR_TRIGGER_SOURCE_B Description changed ("Digital 6", "") - TriggerSource.Digital7 - RSRTM20XX_ATTR_TRIGGER_SOURCE_A, RSRTM20XX_ATTR_TRIGGER_SOURCE_B Description changed ("Digital 7", "") - TriggerSource.Digital8 - RSRTM20XX_ATTR_TRIGGER_SOURCE_A, RSRTM20XX_ATTR_TRIGGER_SOURCE_B Description changed ("Digital 8", "") - TriggerSource.Digital9 - RSRTM20XX_ATTR_TRIGGER_SOURCE_A, RSRTM20XX_ATTR_TRIGGER_SOURCE_B Description changed ("Digital 9", "") - TriggerSource.Digital10 - RSRTM20XX_ATTR_TRIGGER_SOURCE_A, RSRTM20XX_ATTR_TRIGGER_SOURCE_B Description changed ("Digital 10", "") - TriggerSource.Digital11 - RSRTM20XX_ATTR_TRIGGER_SOURCE_A, RSRTM20XX_ATTR_TRIGGER_SOURCE_B Description changed ("Digital 11", "") - TriggerSource.Digital12 - RSRTM20XX_ATTR_TRIGGER_SOURCE_A,

RsRtm20xx Instrument Driver		
Driver history for C#, Visual Basic .NET		
Revision	Date	Note
		RSRTM20XX_ATTR_TRIGGER_SOURCE_B Description changed ("Digital 12", "") - TriggerSource.Digital13 - RSRTM20XX_ATTR_TRIGGER_SOURCE_A, RSRTM20XX_ATTR_TRIGGER_SOURCE_B Description changed ("Digital 13", "") - TriggerSource.Digital14 - RSRTM20XX_ATTR_TRIGGER_SOURCE_A, RSRTM20XX_ATTR_TRIGGER_SOURCE_B Description changed ("Digital 14", "") - TriggerSource.Digital15 - RSRTM20XX_ATTR_TRIGGER_SOURCE_A, RSRTM20XX_ATTR_TRIGGER_SOURCE_B Description changed ("Digital 15", "") - Polarity.Positive - RSRTM20XX_ATTR_TV_TRIGGER_POLARITY, RSRTM20XX_ATTR_WIDTH_POLARITY, RSRTM20XX_ATTR_TRIGGER_TIME_POLARITY, RSRTM20XX_ATTR_TRIGGER_OUT_POLARITY, RSRTM20XX_ATTR_RUNT_TRIGGER_POLARITY, RSRTM20XX_ATTR_PROTOCOL_AUDIO_TRIGGER_WORD_SELECT_SLOPE, RSRTM20XX_ATTR_MASK_TEST_VIOLATION_PULSE_POLARITY, RSRTM20XX_ATTR_SEARCH_TRIGGER_WIDTH_POLARITY, RSRTM20XX_ATTR_PROTOCOL_SSPI_CLOCK_POLARITY, RSRTM20XX_ATTR_PROTOCOL_SSPI_DATA_POLARITY, RSRTM20XX_ATTR_PROTOCOL_UART_POLARITY, RSRTM20XX_ATTR_PARALLEL_BUS_CLOCKED_CS_POLARITY, RSRTM20XX_ATTR_PROTOCOL_MILSTD_POLARITY Description changed ("Positive", "") - Polarity.Negative - RSRTM20XX_ATTR_TV_TRIGGER_POLARITY, RSRTM20XX_ATTR_WIDTH_POLARITY, RSRTM20XX_ATTR_TRIGGER_TIME_POLARITY, RSRTM20XX_ATTR_TRIGGER_OUT_POLARITY, RSRTM20XX_ATTR_RUNT_TRIGGER_POLARITY, RSRTM20XX_ATTR_PROTOCOL_AUDIO_TRIGGER_WORD_SELECT_SLOPE, RSRTM20XX_ATTR_MASK_TEST_VIOLATION_PULSE_POLARITY, RSRTM20XX_ATTR_SEARCH_TRIGGER_WIDTH_POLARITY, RSRTM20XX_ATTR_PROTOCOL_SSPI_CLOCK_POLARITY, RSRTM20XX_ATTR_PROTOCOL_SSPI_DATA_POLARITY, RSRTM20XX_ATTR_PROTOCOL_UART_POLARITY, RSRTM20XX_ATTR_PARALLEL_BUS_CLOCKED_CS_POLARITY, RSRTM20XX_ATTR_PROTOCOL_MILSTD_POLARITY Description changed ("Negative", "") - WidthCondition.Shorter - RSRTM20XX_ATTR_WIDTH_CONDITION, RSRTM20XX_ATTR_TRIGGER_PATTERN_WIDTH_CONDITION, RSRTM20XX_ATTR_TRIGGER_TIME_CONDITION Description changed ("Shorter", "") - WidthCondition.Longer - RSRTM20XX_ATTR_WIDTH_CONDITION, RSRTM20XX_ATTR_TRIGGER_PATTERN_WIDTH_CONDITION, RSRTM20XX_ATTR_TRIGGER_TIME_CONDITION Description changed ("Longer", "") - WidthCondition.Within - RSRTM20XX_ATTR_WIDTH_CONDITION, RSRTM20XX_ATTR_TRIGGER_PATTERN_WIDTH_CONDITION, RSRTM20XX_ATTR_TRIGGER_TIME_CONDITION Description changed ("Within", "") - WidthCondition.Outside - RSRTM20XX_ATTR_WIDTH_CONDITION, RSRTM20XX_ATTR_TRIGGER_PATTERN_WIDTH_CONDITION,

RsRtm20xx Instrument Driver		
Driver history for C#, Visual Basic .NET		
Revision	Date	Note
		<p>RSRTM20XX_ATTR_TRIGGER_TIME_CONDITION</p> <p>Description changed ("Outside", "")</p> <p>- TVTriggerEvent.Even - RSRTM20XX_ATTR_TV_TRIGGER_EVENT</p> <p>Description changed ("Even", "")</p> <p>- TVTriggerEvent.Odd - RSRTM20XX_ATTR_TV_TRIGGER_EVENT</p> <p>Description changed ("Odd", "")</p> <p>- TVTriggerEvent.All - RSRTM20XX_ATTR_TV_TRIGGER_EVENT</p> <p>Description changed ("All", "")</p> <p>- TVTriggerEvent.Line - RSRTM20XX_ATTR_TV_TRIGGER_EVENT</p> <p>Description changed ("Line", "")</p> <p>- TVTriggerEvent.AllLine - RSRTM20XX_ATTR_TV_TRIGGER_EVENT</p> <p>Description changed ("All Line", "")</p> <p>- ChannelPatternCombination.And -</p> <p>Description changed ("And", "")</p> <p>- ChannelPatternCombination.Or -</p> <p>Description changed ("Or", "")</p> <p>- FalseTrue.False -</p> <p>Description changed ("False", "")</p> <p>- FalseTrue.True -</p> <p>Description changed ("True", "")</p> <p>- CursorFunction.Horizontal - RSRTM20XX_ATTR_CURSOR_MEASUREMENT_TYPE</p> <p>Description changed ("Horizontal", "")</p> <p>- CursorFunction.Vertical - RSRTM20XX_ATTR_CURSOR_MEASUREMENT_TYPE</p> <p>Description changed ("Vertical", "")</p> <p>- CursorFunction.Paired - RSRTM20XX_ATTR_CURSOR_MEASUREMENT_TYPE</p> <p>Description changed ("Paired", "")</p> <p>- CursorFunction.HRatio - RSRTM20XX_ATTR_CURSOR_MEASUREMENT_TYPE</p> <p>Description changed ("H Ratio", "")</p> <p>- CursorFunction.VRatio - RSRTM20XX_ATTR_CURSOR_MEASUREMENT_TYPE</p> <p>Description changed ("V Ratio", "")</p> <p>- CursorFunction.CountPositive - RSRTM20XX_ATTR_CURSOR_MEASUREMENT_TYPE</p> <p>Description changed ("Count Positive", "")</p> <p>- CursorFunction.CountNegative - RSRTM20XX_ATTR_CURSOR_MEASUREMENT_TYPE</p> <p>Description changed ("Count Negative", "")</p> <p>- CursorFunction.CountRising - RSRTM20XX_ATTR_CURSOR_MEASUREMENT_TYPE</p> <p>Description changed ("Count Rising", "")</p> <p>- CursorFunction.CountFalling - RSRTM20XX_ATTR_CURSOR_MEASUREMENT_TYPE</p> <p>Description changed ("Count Falling", "")</p> <p>- CursorFunction.Mean - RSRTM20XX_ATTR_CURSOR_MEASUREMENT_TYPE</p> <p>Description changed ("Mean", "")</p> <p>- CursorFunction.RootMean - RSRTM20XX_ATTR_CURSOR_MEASUREMENT_TYPE</p>

RsRtm20xx Instrument Driver		
Driver history for C#, Visual Basic .NET		
Revision	Date	Note
		<ul style="list-style-type: none"> Description changed ("Root Mean", "") - CursorFunction.Rise - RSRTM20XX_ATTR_CURSOR_MEASUREMENT_TYPE Description changed ("Rise", "") - CursorFunction.Fall - RSRTM20XX_ATTR_CURSOR_MEASUREMENT_TYPE Description changed ("Fall", "") - CursorFunction.Peak - RSRTM20XX_ATTR_CURSOR_MEASUREMENT_TYPE Description changed ("Peak", "") - CursorFunction.UpperPeak - RSRTM20XX_ATTR_CURSOR_MEASUREMENT_TYPE Description changed ("Upper Peak", "") - CursorFunction.LowerPeak - RSRTM20XX_ATTR_CURSOR_MEASUREMENT_TYPE Description changed ("Lower Peak", "") - CursorFunction.Burst - RSRTM20XX_ATTR_CURSOR_MEASUREMENT_TYPE Description changed ("Burst", "") - XRatioUnit.Floating - RSRTM20XX_ATTR_CURSOR_X_RATIO_MEASUREMENT_UNIT Description changed ("Floating", "") - XRatioUnit.Percent - RSRTM20XX_ATTR_CURSOR_X_RATIO_MEASUREMENT_UNIT Description changed ("Percent", "") - XRatioUnit.Degree - RSRTM20XX_ATTR_CURSOR_X_RATIO_MEASUREMENT_UNIT Description changed ("Degree", "") - XRatioUnit.Radian - RSRTM20XX_ATTR_CURSOR_X_RATIO_MEASUREMENT_UNIT Description changed ("Radian", "") - YRatioUnit.Floating - RSRTM20XX_ATTR_CURSOR_Y_RATIO_MEASUREMENT_UNIT Description changed ("Floating", "") - YRatioUnit.Percent - RSRTM20XX_ATTR_CURSOR_Y_RATIO_MEASUREMENT_UNIT Description changed ("Percent", "") - RollModeAuto.Off - Description changed ("Off", "") - RollModeAuto.Auto - Description changed ("Auto", "") - Interpolation.SinX - RSRTM20XX_ATTR_INTERPOLATION Description changed ("SinX", "") - Interpolation.Linear - RSRTM20XX_ATTR_INTERPOLATION Description changed ("Linear", "") - Interpolation.SampleHold - RSRTM20XX_ATTR_INTERPOLATION Description changed ("Sample Hold", "") - MeasurementCategory.AmpTime - RSRTM20XX_ATTR_MEASUREMENT_CATEGORY Description changed ("Amplitude And Time", "") - FFTWindowType.Rectangular - RSRTM20XX_ATTR_FFT_WINDOW_TYPE Description changed ("Rectangular", "") - FFTWindowType.Hamming - RSRTM20XX_ATTR_FFT_WINDOW_TYPE Description changed ("Hamming", "")

RsRtm20xx Instrument Driver		
Driver history for C#, Visual Basic .NET		
Revision	Date	Note
		<ul style="list-style-type: none"> - FFTWindowType.Hann - RSRTM20XX_ATTR_FFT_WINDOW_TYPE Description changed ("Hann", "") - FFTWindowType.Blackman - RSRTM20XX_ATTR_FFT_WINDOW_TYPE Description changed ("Blackman", "") - FFTWindowType - RSRTM20XX_ATTR_FFT_WINDOW_TYPE New items: FlatTop - I2CFrameState.Ok - RSRTM20XX_ATTR_PROTOCOL_I2C_FRAME_STATUS Description changed ("Ok", "") - I2CFrameState.Incomplete - RSRTM20XX_ATTR_PROTOCOL_I2C_FRAME_STATUS Description changed ("Incomplete", "") - I2CFrameState.UnexpectedStop - RSRTM20XX_ATTR_PROTOCOL_I2C_FRAME_STATUS Description changed ("Unexpected Stop", "") - I2CFrameState.Insufficient - RSRTM20XX_ATTR_PROTOCOL_I2C_FRAME_STATUS Description changed ("Insufficient", "") - I2CFrameState.Add - RSRTM20XX_ATTR_PROTOCOL_I2C_FRAME_STATUS Description changed ("Add", "") - ProtocolAckBit.Either - RSRTM20XX_ATTR_PROTOCOL_I2C_FRAME_ADDRESS_ACKNOWLEDGE, RSRTM20XX_ATTR_PROTOCOL_I2C_BYTE_ACK_BIT Description changed ("Either", "") - ProtocolAckBit.Ack - RSRTM20XX_ATTR_PROTOCOL_I2C_FRAME_ADDRESS_ACKNOWLEDGE, RSRTM20XX_ATTR_PROTOCOL_I2C_BYTE_ACK_BIT Description changed ("Ack", "") - ProtocolAckBit.NAck - RSRTM20XX_ATTR_PROTOCOL_I2C_FRAME_ADDRESS_ACKNOWLEDGE, RSRTM20XX_ATTR_PROTOCOL_I2C_BYTE_ACK_BIT Description changed ("NAck", "") - ProtocolAckBit.Missing - RSRTM20XX_ATTR_PROTOCOL_I2C_FRAME_ADDRESS_ACKNOWLEDGE, RSRTM20XX_ATTR_PROTOCOL_I2C_BYTE_ACK_BIT Description changed ("Missing", "") - SPIBitOrder.MSBF - RSRTM20XX_ATTR_PROTOCOL_SPI_BIT_ORDER, RSRTM20XX_ATTR_PROTOCOL_SSPI_BIT_ORDER Description changed ("Most significant bit", "") - SPIBitOrder.LSBF - RSRTM20XX_ATTR_PROTOCOL_SPI_BIT_ORDER, RSRTM20XX_ATTR_PROTOCOL_SSPI_BIT_ORDER Description changed ("Least significant bit", "") - ProtocolWfmSource.DigitalChannel1 - RSRTM20XX_ATTR_PROTOCOL_AUDIO_CLOCK_SOURCE, RSRTM20XX_ATTR_PROTOCOL_AUDIO_WS_SOURCE, RSRTM20XX_ATTR_PROTOCOL_AUDIO_DATA_SOURCE Description changed ("Digital Channel 1", "") - ProtocolWfmSource.DigitalChannel2 - RSRTM20XX_ATTR_PROTOCOL_AUDIO_CLOCK_SOURCE, RSRTM20XX_ATTR_PROTOCOL_AUDIO_WS_SOURCE, RSRTM20XX_ATTR_PROTOCOL_AUDIO_DATA_SOURCE Description changed ("Digital Channel 2", "") - ProtocolWfmSource.DigitalChannel3 - RSRTM20XX_ATTR_PROTOCOL_AUDIO_CLOCK_SOURCE, RSRTM20XX_ATTR_PROTOCOL_AUDIO_WS_SOURCE,

RsRtm20xx Instrument Driver		
Driver history for C#, Visual Basic .NET		
Revision	Date	Note
		<p>RSRTM20XX_ATTR_PROTOCOL_AUDIO_DATA_SOURCE</p> <p>Description changed ("Digital Channel 3", "")</p> <ul style="list-style-type: none"> - ProtocolWfmSource.DigitalChannel4 - RSRTM20XX_ATTR_PROTOCOL_AUDIO_CLOCK_SOURCE, RSRTM20XX_ATTR_PROTOCOL_AUDIO_WS_SOURCE, RSRTM20XX_ATTR_PROTOCOL_AUDIO_DATA_SOURCE <p>Description changed ("Digital Channel 4", "")</p> <ul style="list-style-type: none"> - ProtocolWfmSource.DigitalChannel5 - RSRTM20XX_ATTR_PROTOCOL_AUDIO_CLOCK_SOURCE, RSRTM20XX_ATTR_PROTOCOL_AUDIO_WS_SOURCE, RSRTM20XX_ATTR_PROTOCOL_AUDIO_DATA_SOURCE <p>Description changed ("Digital Channel 5", "")</p> <ul style="list-style-type: none"> - ProtocolWfmSource.DigitalChannel6 - RSRTM20XX_ATTR_PROTOCOL_AUDIO_CLOCK_SOURCE, RSRTM20XX_ATTR_PROTOCOL_AUDIO_WS_SOURCE, RSRTM20XX_ATTR_PROTOCOL_AUDIO_DATA_SOURCE <p>Description changed ("Digital Channel 6", "")</p> <ul style="list-style-type: none"> - ProtocolWfmSource.DigitalChannel7 - RSRTM20XX_ATTR_PROTOCOL_AUDIO_CLOCK_SOURCE, RSRTM20XX_ATTR_PROTOCOL_AUDIO_WS_SOURCE, RSRTM20XX_ATTR_PROTOCOL_AUDIO_DATA_SOURCE <p>Description changed ("Digital Channel 7", "")</p> <ul style="list-style-type: none"> - ProtocolWfmSource.DigitalChannel8 - RSRTM20XX_ATTR_PROTOCOL_AUDIO_CLOCK_SOURCE, RSRTM20XX_ATTR_PROTOCOL_AUDIO_WS_SOURCE, RSRTM20XX_ATTR_PROTOCOL_AUDIO_DATA_SOURCE <p>Description changed ("Digital Channel 8", "")</p> <ul style="list-style-type: none"> - ProtocolWfmSource.DigitalChannel9 - RSRTM20XX_ATTR_PROTOCOL_AUDIO_CLOCK_SOURCE, RSRTM20XX_ATTR_PROTOCOL_AUDIO_WS_SOURCE, RSRTM20XX_ATTR_PROTOCOL_AUDIO_DATA_SOURCE <p>Description changed ("Digital Channel 9", "")</p> <ul style="list-style-type: none"> - ProtocolWfmSource.DigitalChannel10 - RSRTM20XX_ATTR_PROTOCOL_AUDIO_CLOCK_SOURCE, RSRTM20XX_ATTR_PROTOCOL_AUDIO_WS_SOURCE, RSRTM20XX_ATTR_PROTOCOL_AUDIO_DATA_SOURCE <p>Description changed ("Digital Channel 10", "")</p> <ul style="list-style-type: none"> - ProtocolWfmSource.DigitalChannel11 - RSRTM20XX_ATTR_PROTOCOL_AUDIO_CLOCK_SOURCE, RSRTM20XX_ATTR_PROTOCOL_AUDIO_WS_SOURCE, RSRTM20XX_ATTR_PROTOCOL_AUDIO_DATA_SOURCE <p>Description changed ("Digital Channel 11", "")</p> <ul style="list-style-type: none"> - ProtocolWfmSource.DigitalChannel12 - RSRTM20XX_ATTR_PROTOCOL_AUDIO_CLOCK_SOURCE, RSRTM20XX_ATTR_PROTOCOL_AUDIO_WS_SOURCE, RSRTM20XX_ATTR_PROTOCOL_AUDIO_DATA_SOURCE <p>Description changed ("Digital Channel 12", "")</p> <ul style="list-style-type: none"> - ProtocolWfmSource.DigitalChannel13 - RSRTM20XX_ATTR_PROTOCOL_AUDIO_CLOCK_SOURCE, RSRTM20XX_ATTR_PROTOCOL_AUDIO_WS_SOURCE, RSRTM20XX_ATTR_PROTOCOL_AUDIO_DATA_SOURCE <p>Description changed ("Digital Channel 13", "")</p> <ul style="list-style-type: none"> - ProtocolWfmSource.DigitalChannel14 - RSRTM20XX_ATTR_PROTOCOL_AUDIO_CLOCK_SOURCE, RSRTM20XX_ATTR_PROTOCOL_AUDIO_WS_SOURCE, RSRTM20XX_ATTR_PROTOCOL_AUDIO_DATA_SOURCE <p>Description changed ("Digital Channel 14", "")</p> <ul style="list-style-type: none"> - ProtocolWfmSource.DigitalChannel15 - RSRTM20XX_ATTR_PROTOCOL_AUDIO_CLOCK_SOURCE,

RsRtm20xx Instrument Driver		
Driver history for C#, Visual Basic .NET		
Revision	Date	Note
		RSRTM20XX_ATTR_PROTOCOL_AUDIO_WS_SOURCE, RSRTM20XX_ATTR_PROTOCOL_AUDIO_DATA_SOURCE Description changed ("Digital Channel 15", "") - SPIDataAlignment.Bit - Description changed ("Bit", "") - SPIDataAlignment.Word - Description changed ("Word", "") - SPIFrameState.OK - RSRTM20XX_ATTR_PROTOCOL_SPI_FRAME_STATUS Description changed ("OK", "") - SPIFrameState.IncompleteFirst - RSRTM20XX_ATTR_PROTOCOL_SPI_FRAME_STATUS Description changed ("Incomplete first", "") - SPIFrameState.IncompleteLast - RSRTM20XX_ATTR_PROTOCOL_SPI_FRAME_STATUS Description changed ("Incomplete last", "") - SPIFrameState.Insufficient - RSRTM20XX_ATTR_PROTOCOL_SPI_FRAME_STATUS Description changed ("Insufficient", "") - UARTParity.None - RSRTM20XX_ATTR_PROTOCOL_UART_PARITY Description changed ("None", "") - UARTParity.Odd - RSRTM20XX_ATTR_PROTOCOL_UART_PARITY Description changed ("Odd", "") - UARTParity.Even - RSRTM20XX_ATTR_PROTOCOL_UART_PARITY Description changed ("Even", "") - UARTStopBits.B1 - RSRTM20XX_ATTR_PROTOCOL_UART_STOP_BITS Description changed ("B1", "") - UARTStopBits.B15 - RSRTM20XX_ATTR_PROTOCOL_UART_STOP_BITS Description changed ("B15", "") - UARTStopBits.B2 - RSRTM20XX_ATTR_PROTOCOL_UART_STOP_BITS Description changed ("B2", "") - UARTTriggerType.BurstStart - RSRTM20XX_ATTR_PROTOCOL_UART_TRIGGER_MODE Description changed ("Burst start", "") - UARTTriggerType.StartBit - RSRTM20XX_ATTR_PROTOCOL_UART_TRIGGER_MODE Description changed ("Start bit", "") - UARTTriggerType.NthSymbol - RSRTM20XX_ATTR_PROTOCOL_UART_TRIGGER_MODE Description changed ("N-th symbol", "") - UARTTriggerType.Symbol - RSRTM20XX_ATTR_PROTOCOL_UART_TRIGGER_MODE Description changed ("Symbol", "") - UARTTriggerType.Pattern - RSRTM20XX_ATTR_PROTOCOL_UART_TRIGGER_MODE Description changed ("Pattern", "") - UARTTriggerType.ParityError - RSRTM20XX_ATTR_PROTOCOL_UART_TRIGGER_MODE Description changed ("Parity error", "") - UARTTriggerType.FrameError - RSRTM20XX_ATTR_PROTOCOL_UART_TRIGGER_MODE Description changed ("Frame error", "")

RsRtm20xx Instrument Driver		
Driver history for C#, Visual Basic .NET		
Revision	Date	Note
		<ul style="list-style-type: none"> - UARTTriggerType.Break - RSRTM20XX_ATTR_PROTOCOL_UART_TRIGGER_MODE Description changed ("Break", "") - SignalStyle.Vectors - RSRTM20XX_ATTR_SIGNAL_STYLE Description changed ("Vectors", "") - SignalStyle.Dots - RSRTM20XX_ATTR_SIGNAL_STYLE Description changed ("Dots", "") - HardcopyDeviceOrientation.Portrait - RSRTM20XX_ATTR_HARDCOPY_DEVICE_ORIENTATION Description changed ("Portrait", "") - HardcopyDeviceOrientation.Landscape - RSRTM20XX_ATTR_HARDCOPY_DEVICE_ORIENTATION Description changed ("Landscape", "") - WfmParameter.Ch1 - RSRTM20XX_ATTR_CURSOR_SOURCE, RSRTM20XX_ATTR_REFERENCE_WAVEFORM_SOURCE Description changed ("Channel 1", "") - WfmParameter.Ch2 - RSRTM20XX_ATTR_CURSOR_SOURCE, RSRTM20XX_ATTR_REFERENCE_WAVEFORM_SOURCE Description changed ("Channel 2", "") - WfmParameter.Ch3 - RSRTM20XX_ATTR_CURSOR_SOURCE, RSRTM20XX_ATTR_REFERENCE_WAVEFORM_SOURCE Description changed ("Channel 3", "") - WfmParameter.Ch4 - RSRTM20XX_ATTR_CURSOR_SOURCE, RSRTM20XX_ATTR_REFERENCE_WAVEFORM_SOURCE Description changed ("Channel 4", "") - WfmParameter.MW1 - RSRTM20XX_ATTR_CURSOR_SOURCE, RSRTM20XX_ATTR_REFERENCE_WAVEFORM_SOURCE Description changed ("Math Waveform 1", "") - WfmParameter.MW2 - RSRTM20XX_ATTR_CURSOR_SOURCE, RSRTM20XX_ATTR_REFERENCE_WAVEFORM_SOURCE Description changed ("Math Waveform 2", "") - WfmParameter.MW3 - RSRTM20XX_ATTR_CURSOR_SOURCE, RSRTM20XX_ATTR_REFERENCE_WAVEFORM_SOURCE Description changed ("Math Waveform 3", "") - WfmParameter.MW4 - RSRTM20XX_ATTR_CURSOR_SOURCE, RSRTM20XX_ATTR_REFERENCE_WAVEFORM_SOURCE Description changed ("Math Waveform 4", "") - WfmParameter.MW5 - RSRTM20XX_ATTR_CURSOR_SOURCE, RSRTM20XX_ATTR_REFERENCE_WAVEFORM_SOURCE Description changed ("Math Waveform 5", "") - WfmParameter.RefW1 - RSRTM20XX_ATTR_CURSOR_SOURCE, RSRTM20XX_ATTR_REFERENCE_WAVEFORM_SOURCE Description changed ("Reference Waveform 1", "") - WfmParameter.RefW2 - RSRTM20XX_ATTR_CURSOR_SOURCE, RSRTM20XX_ATTR_REFERENCE_WAVEFORM_SOURCE Description changed ("Reference Waveform 2", "") - WfmParameter.RefW3 - RSRTM20XX_ATTR_CURSOR_SOURCE,

RsRtm20xx Instrument Driver		
Driver history for C#, Visual Basic .NET		
Revision	Date	Note
		RSRTM20XX_ATTR_REFERENCE_WAVEFORM_SOURCE Description changed ("Reference Waveform 3", "") - WfmParameter.RefW4 - RSRTM20XX_ATTR_CURSOR_SOURCE,
		RSRTM20XX_ATTR_REFERENCE_WAVEFORM_SOURCE Description changed ("Reference Waveform 4", "") - WfmParameter.Digital0 - RSRTM20XX_ATTR_CURSOR_SOURCE,
		RSRTM20XX_ATTR_REFERENCE_WAVEFORM_SOURCE Description changed ("Digital 0", "") - WfmParameter.Digital1 - RSRTM20XX_ATTR_CURSOR_SOURCE,
		RSRTM20XX_ATTR_REFERENCE_WAVEFORM_SOURCE Description changed ("Digital 1", "") - WfmParameter.Digital2 - RSRTM20XX_ATTR_CURSOR_SOURCE,
		RSRTM20XX_ATTR_REFERENCE_WAVEFORM_SOURCE Description changed ("Digital 2", "") - WfmParameter.Digital3 - RSRTM20XX_ATTR_CURSOR_SOURCE,
		RSRTM20XX_ATTR_REFERENCE_WAVEFORM_SOURCE Description changed ("Digital 3", "") - WfmParameter.Digital4 - RSRTM20XX_ATTR_CURSOR_SOURCE,
		RSRTM20XX_ATTR_REFERENCE_WAVEFORM_SOURCE Description changed ("Digital 4", "") - WfmParameter.Digital5 - RSRTM20XX_ATTR_CURSOR_SOURCE,
		RSRTM20XX_ATTR_REFERENCE_WAVEFORM_SOURCE Description changed ("Digital 5", "") - WfmParameter.Digital6 - RSRTM20XX_ATTR_CURSOR_SOURCE,
		RSRTM20XX_ATTR_REFERENCE_WAVEFORM_SOURCE Description changed ("Digital 6", "") - WfmParameter.Digital7 - RSRTM20XX_ATTR_CURSOR_SOURCE,
		RSRTM20XX_ATTR_REFERENCE_WAVEFORM_SOURCE Description changed ("Digital 7", "") - WfmParameter.Digital8 - RSRTM20XX_ATTR_CURSOR_SOURCE,
		RSRTM20XX_ATTR_REFERENCE_WAVEFORM_SOURCE Description changed ("Digital 8", "") - WfmParameter.Digital9 - RSRTM20XX_ATTR_CURSOR_SOURCE,
		RSRTM20XX_ATTR_REFERENCE_WAVEFORM_SOURCE Description changed ("Digital 9", "") - WfmParameter.Digital10 - RSRTM20XX_ATTR_CURSOR_SOURCE,
		RSRTM20XX_ATTR_REFERENCE_WAVEFORM_SOURCE Description changed ("Digital 10", "") - WfmParameter.Digital11 - RSRTM20XX_ATTR_CURSOR_SOURCE,
		RSRTM20XX_ATTR_REFERENCE_WAVEFORM_SOURCE Description changed ("Digital11", "") - WfmParameter.Digital12 - RSRTM20XX_ATTR_CURSOR_SOURCE,
		RSRTM20XX_ATTR_REFERENCE_WAVEFORM_SOURCE Description changed ("Digital 12", "") - WfmParameter.Digital13 - RSRTM20XX_ATTR_CURSOR_SOURCE,

RsRtm20xx Instrument Driver		
Driver history for C#, Visual Basic .NET		
Revision	Date	Note
		<p>RSRTM20XX_ATTR_REFERENCE_WAVEFORM_SOURCE</p> <p>Description changed ("Digital 13", "")</p> <p>- WfmParameter.Digital14 - RSRTM20XX_ATTR_CURSOR_SOURCE,</p> <p>RSRTM20XX_ATTR_REFERENCE_WAVEFORM_SOURCE</p> <p>Description changed ("Digital 14", "")</p> <p>- WfmParameter.Digital15 - RSRTM20XX_ATTR_CURSOR_SOURCE,</p> <p>RSRTM20XX_ATTR_REFERENCE_WAVEFORM_SOURCE</p> <p>Description changed ("Digital 15", "")</p> <p>- WfmParameter.Digital70 - RSRTM20XX_ATTR_CURSOR_SOURCE,</p> <p>RSRTM20XX_ATTR_REFERENCE_WAVEFORM_SOURCE</p> <p>Description changed ("Digital 70", "")</p> <p>- WfmParameter.Digital158 - RSRTM20XX_ATTR_CURSOR_SOURCE,</p> <p>RSRTM20XX_ATTR_REFERENCE_WAVEFORM_SOURCE</p> <p>Description changed ("Digital 158", "")</p> <p>- WfmParameter - RSRTM20XX_ATTR_CURSOR_SOURCE,</p> <p>RSRTM20XX_ATTR_REFERENCE_WAVEFORM_SOURCE</p> <p>New items: Spectrum, XY2, MinHold, MaxHold, Average</p> <p>- I2CAddressAccessBit.Either -</p> <p>Description changed ("Either", "")</p> <p>- I2CAddressAccessBit.ACK -</p> <p>Description changed ("ACK", "")</p> <p>- I2CAddressAccessBit.NACK -</p> <p>Description changed ("NACK", "")</p> <p>- I2CAddressAccessBit.Incomplete -</p> <p>Description changed ("Incomplete", "")</p> <p>- SampleRate.Auto - RSRTM20XX_ATTR_WAVEFORM_RATE</p> <p>Description changed ("Auto", "")</p> <p>- SampleRate.MaxSample - RSRTM20XX_ATTR_WAVEFORM_RATE</p> <p>Description changed ("Max Sample", "")</p> <p>- SampleRate.MaxWaveform - RSRTM20XX_ATTR_WAVEFORM_RATE</p> <p>Description changed ("Max Waveform", "")</p> <p>- ColorBrightness.Normal - RSRTM20XX_ATTR_COLOR_AND_BRIGHTNESS</p> <p>Description changed ("Normal", "")</p> <p>- ColorBrightness.Inverse - RSRTM20XX_ATTR_COLOR_AND_BRIGHTNESS</p> <p>Description changed ("Inverse", "")</p> <p>- ColorBrightness.FrequenctColor - RSRTM20XX_ATTR_COLOR_AND_BRIGHTNESS</p> <p>Description changed ("Frequenct Color", "")</p> <p>- ColorBrightness.InverseColor - RSRTM20XX_ATTR_COLOR_AND_BRIGHTNESS</p> <p>Description changed ("Inverse Color", "")</p> <p>- DiagramMode.YT - RSRTM20XX_ATTR_DIAGRAM_MODE</p> <p>Description changed ("YT", "")</p> <p>- DiagramMode.XY - RSRTM20XX_ATTR_DIAGRAM_MODE</p>

RsRtm20xx Instrument Driver		
Driver history for C#, Visual Basic .NET		
Revision	Date	Note
		<ul style="list-style-type: none"> Description changed ("XY", "") - GridStyle.Lines - RSRTM20XX_ATTR_DIAGRAM_GRID_STYLE <ul style="list-style-type: none"> Description changed ("Lines", "") - GridStyle.Cross - RSRTM20XX_ATTR_DIAGRAM_GRID_STYLE <ul style="list-style-type: none"> Description changed ("Cross", "") - GridStyle.None - RSRTM20XX_ATTR_DIAGRAM_GRID_STYLE <ul style="list-style-type: none"> Description changed ("None", "") - XY2Source.None - RSRTM20XX_ATTR_XY_Y2_SOURCE <ul style="list-style-type: none"> Description changed ("None", "") - XY2Source.Ch1 - RSRTM20XX_ATTR_XY_Y2_SOURCE <ul style="list-style-type: none"> Description changed ("Channel 1", "") - XY2Source.Ch2 - RSRTM20XX_ATTR_XY_Y2_SOURCE <ul style="list-style-type: none"> Description changed ("Channel 2", "") - XY2Source.Ch3 - RSRTM20XX_ATTR_XY_Y2_SOURCE <ul style="list-style-type: none"> Description changed ("Channel 3", "") - XY2Source.Ch4 - RSRTM20XX_ATTR_XY_Y2_SOURCE <ul style="list-style-type: none"> Description changed ("Channel 4", "") - IntensityMode.Analog - RSRTM20XX_ATTR_XY_INTENSITY_CONTROL <ul style="list-style-type: none"> Description changed ("Analog", "") - IntensityMode.Digital - RSRTM20XX_ATTR_XY_INTENSITY_CONTROL <ul style="list-style-type: none"> Description changed ("Digital", "") - IntensityMode.Off - RSRTM20XX_ATTR_XY_INTENSITY_CONTROL <ul style="list-style-type: none"> Description changed ("Off", "") - HardcopyDevice.Mem - RSRTM20XX_ATTR_HARDCOPY_DEVICE_DESTINATION <ul style="list-style-type: none"> Description changed ("Mem", "") - HardcopyDevice.Print - RSRTM20XX_ATTR_HARDCOPY_DEVICE_DESTINATION <ul style="list-style-type: none"> Description changed ("Print", "") - HardcopyDeviceLang.Bmp - RSRTM20XX_ATTR_HARDCOPY_DEVICE_LANGUAGE_OUTPUT_FORMAT <ul style="list-style-type: none"> Description changed ("Bmp", "") - HardcopyDeviceLang.Png - RSRTM20XX_ATTR_HARDCOPY_DEVICE_LANGUAGE_OUTPUT_FORMAT <ul style="list-style-type: none"> Description changed ("Png", "") - PageSize.A4 - RSRTM20XX_ATTR_HARDCOPY_PAGE_SIZE <ul style="list-style-type: none"> Description changed ("A4", "") - PageSize.A5 - RSRTM20XX_ATTR_HARDCOPY_PAGE_SIZE <ul style="list-style-type: none"> Description changed ("A5", "") - PageSize.B5 - RSRTM20XX_ATTR_HARDCOPY_PAGE_SIZE <ul style="list-style-type: none"> Description changed ("B5", "") - PageSize.B6 - RSRTM20XX_ATTR_HARDCOPY_PAGE_SIZE <ul style="list-style-type: none"> Description changed ("B6", "") - PageSize.ExecutiveSize - RSRTM20XX_ATTR_HARDCOPY_PAGE_SIZE <ul style="list-style-type: none"> Description changed ("Executive Size", "")

RsRtm20xx Instrument Driver		
Driver history for C#, Visual Basic .NET		
Revision	Date	Note
		<ul style="list-style-type: none"> - MeasResultRTM.Frequency - Description changed ("Frequency", "") - MeasResultRTM.Period - Description changed ("Period", "") - MeasResultRTM.Peak - Description changed ("Peak", "") - MeasResultRTM.UPeak - Description changed ("UPeak", "") - MeasResultRTM.LPeak - Description changed ("LPeak", "") - MeasResultRTM.PP - Description changed ("PPCount", "") - MeasResultRTM.NP - Description changed ("NPCount", "") - MeasResultRTM.RE - Description changed ("RECount", "") - MeasResultRTM.High - Description changed ("High", "") - MeasResultRTM.Low - Description changed ("Low", "") - MeasResultRTM.Amplitude - Description changed ("Amplitude", "") - MeasResultRTM.Mean - Description changed ("Mean", "") - MeasResultRTM.RMS - Description changed ("RMS", "") - MeasResultRTM.RTime - Description changed ("RTime", "") - MeasResultRTM.FTime - Description changed ("FTime", "") - MeasResultRTM.PDC - Description changed ("PDCycle", "") - MeasResultRTM.NDC - Description changed ("NDCycle", "") - MeasResultRTM.PPWidth - Description changed ("PPWidth", "") - MeasResultRTM.NPWidth - Description changed ("NPWidth", "") - MeasResultRTM.CYCMean - Description changed ("CYCMean", "") - MeasResultRTM.CYCRms -

RsRtm20xx Instrument Driver		
Driver history for C#, Visual Basic .NET		
Revision	Date	Note
		<ul style="list-style-type: none"> Description changed ("CYCRms", "") - MeasResultRTM.STDDev - <ul style="list-style-type: none"> Description changed ("STDDev", "") - MeasResultRTM.TFrequency - <ul style="list-style-type: none"> Description changed ("TFrequency", "") - MeasResultRTM.TPeriod - <ul style="list-style-type: none"> Description changed ("TPeriod", "") - ChannelRTM.Ch1 - <ul style="list-style-type: none"> Description changed ("Channel 1", "") - ChannelRTM.Ch2 - <ul style="list-style-type: none"> Description changed ("Channel 2", "") - ChannelRTM.Ch3 - <ul style="list-style-type: none"> Description changed ("Channel 3", "") - ChannelRTM.Ch4 - <ul style="list-style-type: none"> Description changed ("Channel 4", "") - MaskCondition.Run - RSRTM20XX_ATTR_MASK_TEST <ul style="list-style-type: none"> Description changed ("Run", "") - MaskCondition.Stop - RSRTM20XX_ATTR_MASK_TEST <ul style="list-style-type: none"> Description changed ("Stop", "") - MaskCondition.Pause - RSRTM20XX_ATTR_MASK_TEST <ul style="list-style-type: none"> Description changed ("Pause", "") - ButtonAction.NoAction - RSRTM20XX_ATTR_PROBE_MICRO_BUTTON_ACTION <ul style="list-style-type: none"> Description changed ("No Action", "") - ButtonAction.Continuous - RSRTM20XX_ATTR_PROBE_MICRO_BUTTON_ACTION <ul style="list-style-type: none"> Description changed ("Continuous", "") - ButtonAction.RunSingle - RSRTM20XX_ATTR_PROBE_MICRO_BUTTON_ACTION <ul style="list-style-type: none"> Description changed ("Run single", "") - ButtonAction.Autoset - RSRTM20XX_ATTR_PROBE_MICRO_BUTTON_ACTION <ul style="list-style-type: none"> Description changed ("Autoset", "") - TriggerCoupling.DC - RSRTM20XX_ATTR_TRIGGER_COUPLING <ul style="list-style-type: none"> Description changed ("DC", "") - TriggerCoupling.AC - RSRTM20XX_ATTR_TRIGGER_COUPLING <ul style="list-style-type: none"> Description changed ("AC", "") - TriggerCoupling.HighFrequency - RSRTM20XX_ATTR_TRIGGER_COUPLING <ul style="list-style-type: none"> Description changed ("High frequency", "") - I2CAccessBit.Read - RSRTM20XX_ATTR_PROTOCOL_I2C_TRIGGER_ACCESS <ul style="list-style-type: none"> Description changed ("Read", "") - I2CAccessBit.Write - RSRTM20XX_ATTR_PROTOCOL_I2C_TRIGGER_ACCESS <ul style="list-style-type: none"> Description changed ("Write", "") - AddressLength.Normal - RSRTM20XX_ATTR_PROTOCOL_I2C_TRIGGER_ADDRESS_TYPE <ul style="list-style-type: none"> Description changed ("Normal", "")

RsRtm20xx Instrument Driver		
Driver history for C#, Visual Basic .NET		
Revision	Date	Note
		<ul style="list-style-type: none"> - AddressLength.Extended - RSRTM20XX_ATTR_PROTOCOL_I2C_TRIGGER_ADDRESS_TYPE Description changed ("Extended", "") - I2CTrgType.Start - RSRTM20XX_ATTR_PROTOCOL_I2C_TRIGGER_MODE Description changed ("Start", "") - I2CTrgType.Restart - RSRTM20XX_ATTR_PROTOCOL_I2C_TRIGGER_MODE Description changed ("Restart", "") - I2CTrgType.Stop - RSRTM20XX_ATTR_PROTOCOL_I2C_TRIGGER_MODE Description changed ("Stop", "") - I2CTrgType.ModeMissing - RSRTM20XX_ATTR_PROTOCOL_I2C_TRIGGER_MODE Description changed ("Mode Missing", "") - I2CTrgType.Pattern - RSRTM20XX_ATTR_PROTOCOL_I2C_TRIGGER_MODE Description changed ("Pattern", "") - HysteresisMode.Auto - RSRTM20XX_ATTR_TRIGGER_HYSTERESIS_A, RSRTM20XX_ATTR_TRIGGER_HYSTERESIS_B Description changed ("Auto", "") - HysteresisMode.Small - RSRTM20XX_ATTR_TRIGGER_HYSTERESIS_A, RSRTM20XX_ATTR_TRIGGER_HYSTERESIS_B Description changed ("Small", "") - HysteresisMode.Medium - RSRTM20XX_ATTR_TRIGGER_HYSTERESIS_A, RSRTM20XX_ATTR_TRIGGER_HYSTERESIS_B Description changed ("Medium", "") - HysteresisMode.Large - RSRTM20XX_ATTR_TRIGGER_HYSTERESIS_A, RSRTM20XX_ATTR_TRIGGER_HYSTERESIS_B Description changed ("Large", "") - HysteresisMode - RSRTM20XX_ATTR_TRIGGER_HYSTERESIS_A, RSRTM20XX_ATTR_TRIGGER_HYSTERESIS_B New items: Manual - TriggerModifier.Auto - RSRTM20XX_ATTR_TRIGGER_MODIFIER_A, RSRTM20XX_ATTR_TRIGGER_MODIFIER_B Description changed ("Auto", "") - TriggerModifier.Normal - RSRTM20XX_ATTR_TRIGGER_MODIFIER_A, RSRTM20XX_ATTR_TRIGGER_MODIFIER_B Description changed ("Normal", "") - TriggerModifier.Delay - RSRTM20XX_ATTR_TRIGGER_MODIFIER_A, RSRTM20XX_ATTR_TRIGGER_MODIFIER_B Description changed ("Delay", "") - TriggerModifier.Events - RSRTM20XX_ATTR_TRIGGER_MODIFIER_A, RSRTM20XX_ATTR_TRIGGER_MODIFIER_B Description changed ("Events", "") - TrgPatternFunction.And - RSRTM20XX_ATTR_TRIGGER_PATTERN_FUNCTION Description changed ("And", "") - TrgPatternFunction.Or - RSRTM20XX_ATTR_TRIGGER_PATTERN_FUNCTION Description changed ("Or", "")

RsRtm20xx Instrument Driver		
Driver history for C#, Visual Basic .NET		
Revision	Date	Note
		<ul style="list-style-type: none"> - SPITrgType.Start - RSRTM20XX_ATTR_PROTOCOL_SPI_TRIGGER_MODE Description changed ("Start", "") - SPITrgType.End - RSRTM20XX_ATTR_PROTOCOL_SPI_TRIGGER_MODE Description changed ("End", "") - SPITrgType.nth - RSRTM20XX_ATTR_PROTOCOL_SPI_TRIGGER_MODE Description changed ("nth", "") - SPITrgType.Pattern - RSRTM20XX_ATTR_PROTOCOL_SPI_TRIGGER_MODE Description changed ("Pattern", "") - TriggerType.Edge - RSRTM20XX_ATTR_TRIGGER_TYPE_A Description changed ("Edge", "") - TriggerType.Width - RSRTM20XX_ATTR_TRIGGER_TYPE_A Description changed ("Width", "") - TriggerType.Video - RSRTM20XX_ATTR_TRIGGER_TYPE_A Description changed ("Video", "") - TriggerType.Pattern - RSRTM20XX_ATTR_TRIGGER_TYPE_A Description changed ("Pattern", "") - TriggerType.Bus - RSRTM20XX_ATTR_TRIGGER_TYPE_A Description changed ("Bus", "") - TriggerType.RiseTime - RSRTM20XX_ATTR_TRIGGER_TYPE_A Description changed ("RiseTime", "") - TriggerType.Runt - RSRTM20XX_ATTR_TRIGGER_TYPE_A Description changed ("Runt", "") - TVStandard.PAL - RSRTM20XX_ATTR_TV_STANDARD Description changed ("PAL", "") - TVStandard.NTSC - RSRTM20XX_ATTR_TV_STANDARD Description changed ("NTSC", "") - TVStandard.Secam - RSRTM20XX_ATTR_TV_STANDARD Description changed ("Secam", "") - TVStandard.PALM - RSRTM20XX_ATTR_TV_STANDARD Description changed ("PALM", "") - TVStandard.I576 - RSRTM20XX_ATTR_TV_STANDARD Description changed ("I576", "") - TVStandard.P720 - RSRTM20XX_ATTR_TV_STANDARD Description changed ("P720", "") - TVStandard.P1080 - RSRTM20XX_ATTR_TV_STANDARD Description changed ("P1080", "") - TVStandard.I1080 - RSRTM20XX_ATTR_TV_STANDARD Description changed ("I1080", "") - UARTTrgMode.BurstStart - Description changed ("Burst start", "") - UARTTrgMode.StartBit -

RsRtm20xx Instrument Driver		
Driver history for C#, Visual Basic .NET		
Revision	Date	Note
		<ul style="list-style-type: none"> Description changed ("Start bit", "") - UARTTrgMode.nthSymbol - <ul style="list-style-type: none"> Description changed ("nth symbol", "") - UARTTrgMode.Symbol - <ul style="list-style-type: none"> Description changed ("Symbol", "") - UARTTrgMode.Pattern - <ul style="list-style-type: none"> Description changed ("Pattern", "") - UARTTrgMode.ParityError - <ul style="list-style-type: none"> Description changed ("Parity Error", "") - UARTTrgMode.FrameError - <ul style="list-style-type: none"> Description changed ("Frame Error", "") - UARTTrgMode.Bre - <ul style="list-style-type: none"> Description changed ("Bre", "") - ColorScheme.Color - RSRTM20XX_ATTR_HARDCOPY_COLOR_SCHEME <ul style="list-style-type: none"> Description changed ("Color", "") - ColorScheme.Grayscale - RSRTM20XX_ATTR_HARDCOPY_COLOR_SCHEME <ul style="list-style-type: none"> Description changed ("Grayscale", "") - ColorScheme.Inverted - RSRTM20XX_ATTR_HARDCOPY_COLOR_SCHEME <ul style="list-style-type: none"> Description changed ("Inverted", "") - AcquisitionType.Sample - RSRTM20XX_ATTR_ACQUISITION_TYPE <ul style="list-style-type: none"> Description changed ("Sample", "") - AcquisitionType.Peak - RSRTM20XX_ATTR_ACQUISITION_TYPE <ul style="list-style-type: none"> Description changed ("Peak", "") - AcquisitionType.HighResolution - RSRTM20XX_ATTR_ACQUISITION_TYPE <ul style="list-style-type: none"> Description changed ("High resolution", "") - HardcopyLang.Gdi - <ul style="list-style-type: none"> Description changed ("Gdi", "") - HardcopyLang.Bmp - <ul style="list-style-type: none"> Description changed ("Bmp", "") - HardcopyLang.Png - <ul style="list-style-type: none"> Description changed ("Png", "") - ProtocolHeight.Small - RSRTM20XX_ATTR_DIGITAL_VERTICAL_CHANNEL_SIZE, RSRTM20XX_ATTR_PROTOCOL_DISPLAY_HEIGHT <ul style="list-style-type: none"> Description changed ("Small", "") - ProtocolHeight.Medium - RSRTM20XX_ATTR_DIGITAL_VERTICAL_CHANNEL_SIZE, RSRTM20XX_ATTR_PROTOCOL_DISPLAY_HEIGHT <ul style="list-style-type: none"> Description changed ("Medium", "") - ProtocolHeight.Large - RSRTM20XX_ATTR_DIGITAL_VERTICAL_CHANNEL_SIZE, RSRTM20XX_ATTR_PROTOCOL_DISPLAY_HEIGHT <ul style="list-style-type: none"> Description changed ("Large", "") - ProtocolHeight - RSRTM20XX_ATTR_DIGITAL_VERTICAL_CHANNEL_SIZE, RSRTM20XX_ATTR_PROTOCOL_DISPLAY_HEIGHT

RsRtm20xx Instrument Driver		
Driver history for C#, Visual Basic .NET		
Revision	Date	Note
		<p>New items: DIV1, DIV2, DIV4, DIV8</p> <ul style="list-style-type: none"> - RelativeMode.Ten - RSRTM20XX_ATTR_MEAS_RELATIVE_MODE Description changed ("Ten", "") - RelativeMode.Twenty - RSRTM20XX_ATTR_MEAS_RELATIVE_MODE Description changed ("Twenty", "") - RelativeMode.Five - RSRTM20XX_ATTR_MEAS_RELATIVE_MODE Description changed ("Five", "") - RelativeMode.User - RSRTM20XX_ATTR_MEAS_RELATIVE_MODE Description changed ("User", "") - ChannelPolarity.Normal - RSRTM20XX_ATTR_CHANNEL_POLARITY Description changed ("Normal", "") - ChannelPolarity.Inverted - RSRTM20XX_ATTR_CHANNEL_POLARITY Description changed ("Inverted", "") - ExternalTrgCoupling.Ac - RSRTM20XX_ATTR_EXTERNAL_TRIGGER_COUPLING Description changed ("AC", "") - ExternalTrgCoupling.Dc - RSRTM20XX_ATTR_EXTERNAL_TRIGGER_COUPLING Description changed ("DC", "") - MeasCategory.AmpTime - Description changed ("Amp Time", "") - SearchCondition.Edge - RSRTM20XX_ATTR_SEARCH_CONDITION Description changed ("Edge", "") - SearchCondition.Width - RSRTM20XX_ATTR_SEARCH_CONDITION Description changed ("Width", "") - SearchCondition.Peak - RSRTM20XX_ATTR_SEARCH_CONDITION Description changed ("Peak", "") - SearchCondition.Runt - RSRTM20XX_ATTR_SEARCH_CONDITION Description changed ("Runt", "") - SearchCondition.RiseTime - RSRTM20XX_ATTR_SEARCH_CONDITION Description changed ("Rise Time", "") - SearchCondition.Data2Clock - RSRTM20XX_ATTR_SEARCH_CONDITION Description changed ("Data2Clock", "") - SearchCondition.Pattern - RSRTM20XX_ATTR_SEARCH_CONDITION Description changed ("Pattern", "") - SearchCondition.Protocol - RSRTM20XX_ATTR_SEARCH_CONDITION Description changed ("Protocol", "") - SearchSource.Ch1 - RSRTM20XX_ATTR_SEARCH_SOURCE, RSRTM20XX_ATTR_SEARCH_TRIGGER_D2C_CLOCK_SOURCE Description changed ("Channel Waveform 1", "") - SearchSource.Ch2 - RSRTM20XX_ATTR_SEARCH_SOURCE, RSRTM20XX_ATTR_SEARCH_TRIGGER_D2C_CLOCK_SOURCE Description changed ("Channel Waveform 2", "") - SearchSource.Ch3 - RSRTM20XX_ATTR_SEARCH_SOURCE,

RsRtm20xx Instrument Driver		
Driver history for C#, Visual Basic .NET		
Revision	Date	Note
		RSRTM20XX_ATTR_SEARCH_TRIGGER_D2C_CLOCK_SOURCE Description changed ("Channel Waveform 3", "") - SearchSource.Ch4 - RSRTM20XX_ATTR_SEARCH_SOURCE, RSRTM20XX_ATTR_SEARCH_TRIGGER_D2C_CLOCK_SOURCE Description changed ("Channel Waveform 4", "") - SearchSource.Mw1 - RSRTM20XX_ATTR_SEARCH_SOURCE, RSRTM20XX_ATTR_SEARCH_TRIGGER_D2C_CLOCK_SOURCE Description changed ("Math Waveform 1", "") - SearchSource.Mw2 - RSRTM20XX_ATTR_SEARCH_SOURCE, RSRTM20XX_ATTR_SEARCH_TRIGGER_D2C_CLOCK_SOURCE Description changed ("Math Waveform 2", "") - SearchSource.Mw3 - RSRTM20XX_ATTR_SEARCH_SOURCE, RSRTM20XX_ATTR_SEARCH_TRIGGER_D2C_CLOCK_SOURCE Description changed ("Math Waveform 3", "") - SearchSource.Mw4 - RSRTM20XX_ATTR_SEARCH_SOURCE, RSRTM20XX_ATTR_SEARCH_TRIGGER_D2C_CLOCK_SOURCE Description changed ("Math Waveform 4", "") - SearchSource.Rw1 - RSRTM20XX_ATTR_SEARCH_SOURCE, RSRTM20XX_ATTR_SEARCH_TRIGGER_D2C_CLOCK_SOURCE Description changed ("Reference Waveform 1", "") - SearchSource.Rw2 - RSRTM20XX_ATTR_SEARCH_SOURCE, RSRTM20XX_ATTR_SEARCH_TRIGGER_D2C_CLOCK_SOURCE Description changed ("Reference Waveform 2", "") - SearchSource.Rw3 - RSRTM20XX_ATTR_SEARCH_SOURCE, RSRTM20XX_ATTR_SEARCH_TRIGGER_D2C_CLOCK_SOURCE Description changed ("Reference Waveform 3", "") - SearchSource.Rw4 - RSRTM20XX_ATTR_SEARCH_SOURCE, RSRTM20XX_ATTR_SEARCH_TRIGGER_D2C_CLOCK_SOURCE Description changed ("Reference Waveform 4", "") - SearchSource.SerialBus1 - RSRTM20XX_ATTR_SEARCH_SOURCE, RSRTM20XX_ATTR_SEARCH_TRIGGER_D2C_CLOCK_SOURCE Description changed ("SerialBus 1", "") - SearchSource.SerialBus2 - RSRTM20XX_ATTR_SEARCH_SOURCE, RSRTM20XX_ATTR_SEARCH_TRIGGER_D2C_CLOCK_SOURCE Description changed ("SerialBus 2", "") - SearchSource.SerialBus3 - RSRTM20XX_ATTR_SEARCH_SOURCE, RSRTM20XX_ATTR_SEARCH_TRIGGER_D2C_CLOCK_SOURCE Description changed ("SerialBus 3", "") - SearchSource.SerialBus4 - RSRTM20XX_ATTR_SEARCH_SOURCE, RSRTM20XX_ATTR_SEARCH_TRIGGER_D2C_CLOCK_SOURCE Description changed ("SerialBus 4", "") - SearchSlope.Positive - RSRTM20XX_ATTR_SEARCH_TRIGGER_EDGE_SLOPE, RSRTM20XX_ATTR_SEARCH_TRIGGER_PEAK_POLARITY, RSRTM20XX_ATTR_SEARCH_TRIGGER_RISE_TIME_POLARITY, RSRTM20XX_ATTR_SEARCH_TRIGGER_RUNT_POLARITY,

RsRtm20xx Instrument Driver		
Driver history for C#, Visual Basic .NET		
Revision	Date	Note
		<p>RSRTM20XX_ATTR_SEARCH_TRIGGER_D2C_POLARITY</p> <p>Description changed ("Positive", "")</p> <ul style="list-style-type: none"> - SearchSlope.Negative - RSRTM20XX_ATTR_SEARCH_TRIGGER_EDGE_SLOPE, RSRTM20XX_ATTR_SEARCH_TRIGGER_PEAK_POLARITY, RSRTM20XX_ATTR_SEARCH_TRIGGER_RISE_TIME_POLARITY, RSRTM20XX_ATTR_SEARCH_TRIGGER_RUNT_POLARITY, RSRTM20XX_ATTR_SEARCH_TRIGGER_D2C_POLARITY <p>Description changed ("Negative", "")</p> <ul style="list-style-type: none"> - SearchSlope.Either - RSRTM20XX_ATTR_SEARCH_TRIGGER_EDGE_SLOPE, RSRTM20XX_ATTR_SEARCH_TRIGGER_PEAK_POLARITY, RSRTM20XX_ATTR_SEARCH_TRIGGER_RISE_TIME_POLARITY, RSRTM20XX_ATTR_SEARCH_TRIGGER_RUNT_POLARITY, RSRTM20XX_ATTR_SEARCH_TRIGGER_D2C_POLARITY <p>Description changed ("Either", "")</p> <ul style="list-style-type: none"> - SearchRange.Shorter - RSRTM20XX_ATTR_SEARCH_TRIGGER_WIDTH_RANGE, RSRTM20XX_ATTR_SEARCH_TRIGGER_RISE_TIME_RANGE, RSRTM20XX_ATTR_SEARCH_TRIGGER_RUNT_RANGE, RSRTM20XX_ATTR_SEARCH_TRIGGER_PATTERN_COMPARISON <p>Description changed ("Shorter", "")</p> <ul style="list-style-type: none"> - SearchRange.Longer - RSRTM20XX_ATTR_SEARCH_TRIGGER_WIDTH_RANGE, RSRTM20XX_ATTR_SEARCH_TRIGGER_RISE_TIME_RANGE, RSRTM20XX_ATTR_SEARCH_TRIGGER_RUNT_RANGE, RSRTM20XX_ATTR_SEARCH_TRIGGER_PATTERN_COMPARISON <p>Description changed ("Longer", "")</p> <ul style="list-style-type: none"> - SearchRange.Within - RSRTM20XX_ATTR_SEARCH_TRIGGER_WIDTH_RANGE, RSRTM20XX_ATTR_SEARCH_TRIGGER_RISE_TIME_RANGE, RSRTM20XX_ATTR_SEARCH_TRIGGER_RUNT_RANGE, RSRTM20XX_ATTR_SEARCH_TRIGGER_PATTERN_COMPARISON <p>Description changed ("Within", "")</p> <ul style="list-style-type: none"> - SearchRange.Outside - RSRTM20XX_ATTR_SEARCH_TRIGGER_WIDTH_RANGE, RSRTM20XX_ATTR_SEARCH_TRIGGER_RISE_TIME_RANGE, RSRTM20XX_ATTR_SEARCH_TRIGGER_RUNT_RANGE, RSRTM20XX_ATTR_SEARCH_TRIGGER_PATTERN_COMPARISON <p>Description changed ("Outside", "")</p> <ul style="list-style-type: none"> - ScallingUnit.Linear - RSRTM20XX_ATTR_FFT_SCALING_UNIT <p>Description changed ("Linear", "")</p> <ul style="list-style-type: none"> - ScallingUnit.DBM - RSRTM20XX_ATTR_FFT_SCALING_UNIT <p>Description changed ("DBM", "")</p> <ul style="list-style-type: none"> - ScallingUnit.DBV - RSRTM20XX_ATTR_FFT_SCALING_UNIT <p>Description changed ("DBV", "")</p> <ul style="list-style-type: none"> - ProbeUnit.V - RSRTM20XX_ATTR_PROBE_ATTENUATION_UNIT <p>Description changed ("V", "")</p> <ul style="list-style-type: none"> - ProbeUnit.A - RSRTM20XX_ATTR_PROBE_ATTENUATION_UNIT <p>Description changed ("A", "")</p> <ul style="list-style-type: none"> - WfmSamplesRange.Default - RSRTM20XX_ATTR_HORZ_RECORD_LENGTH <p>Description changed ("Default", "")</p>

RsRtm20xx Instrument Driver		
Driver history for C#, Visual Basic .NET		
Revision	Date	Note
		<ul style="list-style-type: none"> - WfmSamplesRange.Maximum - RSRTM20XX_ATTR_HORZ_RECORD_LENGTH Description changed ("Maximum", "") - WfmSamplesRange.DisplayMaximum - RSRTM20XX_ATTR_HORZ_RECORD_LENGTH Description changed ("Display Maximum", "") - MaskTestActionExe.Off - RSRTM20XX_ATTR_MASK_TEST_ACTION_BEEP, RSRTM20XX_ATTR_MASK_TEST_ACTION_STOP, RSRTM20XX_ATTR_MASK_TEST_ACTION_SCREENSHOT, RSRTM20XX_ATTR_MASK_TEST_ACTION_PRINT, RSRTM20XX_ATTR_MASK_TEST_ACTION_SAVES_WAVEFORM, RSRTM20XX_ATTR_MASK_TEST_ACTION_PULSE Description changed ("Off", "") - MaskTestActionExe.Each - RSRTM20XX_ATTR_MASK_TEST_ACTION_BEEP, RSRTM20XX_ATTR_MASK_TEST_ACTION_STOP, RSRTM20XX_ATTR_MASK_TEST_ACTION_SCREENSHOT, RSRTM20XX_ATTR_MASK_TEST_ACTION_PRINT, RSRTM20XX_ATTR_MASK_TEST_ACTION_SAVES_WAVEFORM, RSRTM20XX_ATTR_MASK_TEST_ACTION_PULSE Description changed ("Each", "") - MaskTestActionExe.Single - RSRTM20XX_ATTR_MASK_TEST_ACTION_BEEP, RSRTM20XX_ATTR_MASK_TEST_ACTION_STOP, RSRTM20XX_ATTR_MASK_TEST_ACTION_SCREENSHOT, RSRTM20XX_ATTR_MASK_TEST_ACTION_PRINT, RSRTM20XX_ATTR_MASK_TEST_ACTION_SAVES_WAVEFORM, RSRTM20XX_ATTR_MASK_TEST_ACTION_PULSE Description changed ("Single", "") - MaskTestActionExe.Cyclic - RSRTM20XX_ATTR_MASK_TEST_ACTION_BEEP, RSRTM20XX_ATTR_MASK_TEST_ACTION_STOP, RSRTM20XX_ATTR_MASK_TEST_ACTION_SCREENSHOT, RSRTM20XX_ATTR_MASK_TEST_ACTION_PRINT, RSRTM20XX_ATTR_MASK_TEST_ACTION_SAVES_WAVEFORM, RSRTM20XX_ATTR_MASK_TEST_ACTION_PULSE Description changed ("Cyclic", "") - SearchTrgPatternCombination.AND - RSRTM20XX_ATTR_SEARCH_TRIGGER_PATTERN_COMBINATION Description changed ("AND", "") - SearchTrgPatternCombination.OR - RSRTM20XX_ATTR_SEARCH_TRIGGER_PATTERN_COMBINATION Description changed ("OR", "") - SearchTrgPatternCombination.NAND - RSRTM20XX_ATTR_SEARCH_TRIGGER_PATTERN_COMBINATION Description changed ("NAND", "") - SearchTrgPatternCombination.NOR - RSRTM20XX_ATTR_SEARCH_TRIGGER_PATTERN_COMBINATION Description changed ("NOR", "") - SearchGateMode.Off - RSRTM20XX_ATTR_SEARCH_GATE_MODE Description changed ("All", "") - SearchGateMode.Display - RSRTM20XX_ATTR_SEARCH_GATE_MODE Description changed ("Display", "")

RsRtm20xx Instrument Driver		
Driver history for C#, Visual Basic .NET		
Revision	Date	Note
		<ul style="list-style-type: none"> - SearchGateMode.User - RSRTM20XX_ATTR_SEARCH_GATE_MODE Description changed ("User", "") - SPITrgSource.MISO - Description changed ("MISO", "") - SPITrgSource.MOSI - Description changed ("MOSI", "") - UARTTrgSource.Rx - Description changed ("Rx", "") - UARTTrgSource.Tx - Description changed ("Tx", "") - LINStandard.Auto - RSRTM20XX_ATTR_PROTOCOL_LIN_STANDARD Description changed ("Auto", "") - LINStandard.V1x - RSRTM20XX_ATTR_PROTOCOL_LIN_STANDARD Description changed ("v 1.x", "") - LINStandard.V2x - RSRTM20XX_ATTR_PROTOCOL_LIN_STANDARD Description changed ("v 2.x", "") - LINStandard.J2602 - RSRTM20XX_ATTR_PROTOCOL_LIN_STANDARD Description changed ("J2602", "") - LINTrgMode.Start - RSRTM20XX_ATTR_PROTOCOL_LIN_TRIGGER_MODE Description changed ("Start", "") - LINTrgMode.ID - RSRTM20XX_ATTR_PROTOCOL_LIN_TRIGGER_MODE Description changed ("Identifier", "") - LINTrgMode.IDData - RSRTM20XX_ATTR_PROTOCOL_LIN_TRIGGER_MODE Description changed ("Identifier + Data", "") - LINTrgMode.Wakeup - RSRTM20XX_ATTR_PROTOCOL_LIN_TRIGGER_MODE Description changed ("Wakeup Frame", "") - LINTrgMode.ErrorCondition - RSRTM20XX_ATTR_PROTOCOL_LIN_TRIGGER_MODE Description changed ("Error Condition", "") - SearchEvent.Frame - RSRTM20XX_ATTR_PROTOCOL_LIN_SEARCH_EVENT, RSRTM20XX_ATTR_PROTOCOL_CAN_SEARCH_EVENT Description changed ("Frame", "") - SearchEvent.Error - RSRTM20XX_ATTR_PROTOCOL_LIN_SEARCH_EVENT, RSRTM20XX_ATTR_PROTOCOL_CAN_SEARCH_EVENT Description changed ("Error", "") - SearchEvent.ID - RSRTM20XX_ATTR_PROTOCOL_LIN_SEARCH_EVENT, RSRTM20XX_ATTR_PROTOCOL_CAN_SEARCH_EVENT Description changed ("Identifier", "") - SearchEvent.IDandData - RSRTM20XX_ATTR_PROTOCOL_LIN_SEARCH_EVENT, RSRTM20XX_ATTR_PROTOCOL_CAN_SEARCH_EVENT Description changed ("ID and Data", "") - SearchEvent.IDError - RSRTM20XX_ATTR_PROTOCOL_LIN_SEARCH_EVENT, RSRTM20XX_ATTR_PROTOCOL_CAN_SEARCH_EVENT

RsRtm20xx Instrument Driver		
Driver history for C#, Visual Basic .NET		
Revision	Date	Note
		<p>Description changed ("ID Error", "")</p> <ul style="list-style-type: none"> - LINSearchFrameSetup.Start - RSRTM20XX_ATTR_PROTOCOL_LIN_SEARCH_FRAME_SETUP Description changed ("Start", "") - LINSearchFrameSetup.Wakeup - RSRTM20XX_ATTR_PROTOCOL_LIN_SEARCH_FRAME_SETUP Description changed ("Wakeup", "") - CANLineType.CANLow - RSRTM20XX_ATTR_PROTOCOL_CAN_LINE_TYPE Description changed ("CAN-Low", "") - CANLineType.CANHigh - RSRTM20XX_ATTR_PROTOCOL_CAN_LINE_TYPE Description changed ("CAN-High", "") - CANTrgMode.Start - RSRTM20XX_ATTR_PROTOCOL_CAN_TRIGGER_MODE Description changed ("Start", "") - CANTrgMode.End - RSRTM20XX_ATTR_PROTOCOL_CAN_TRIGGER_MODE Description changed ("End", "") - CANTrgMode.Identifier - RSRTM20XX_ATTR_PROTOCOL_CAN_TRIGGER_MODE Description changed ("Identifier", "") - CANTrgMode.IdentifierData - RSRTM20XX_ATTR_PROTOCOL_CAN_TRIGGER_MODE Description changed ("Identifier + Data", "") - CANTrgMode.Type - RSRTM20XX_ATTR_PROTOCOL_CAN_TRIGGER_MODE Description changed ("Frame Type", "") - CANTrgMode.Error - RSRTM20XX_ATTR_PROTOCOL_CAN_TRIGGER_MODE Description changed ("Error Condition", "") - CANTrgFrameType.Data - RSRTM20XX_ATTR_PROTOCOL_CAN_TRIGGER_FRAME_TYPE Description changed ("Data", "") - CANTrgFrameType.Remote - RSRTM20XX_ATTR_PROTOCOL_CAN_TRIGGER_FRAME_TYPE Description changed ("Remote", "") - CANTrgFrameType.Error - RSRTM20XX_ATTR_PROTOCOL_CAN_TRIGGER_FRAME_TYPE Description changed ("Error", "") - CANTrgFrameType.Overload - RSRTM20XX_ATTR_PROTOCOL_CAN_TRIGGER_FRAME_TYPE Description changed ("Over Load", "") - CANTrgFrameType.Any - RSRTM20XX_ATTR_PROTOCOL_CAN_TRIGGER_FRAME_TYPE Description changed ("Any", "") - CANIDType.B11 - RSRTM20XX_ATTR_PROTOCOL_CAN_TRIGGER_ID_TYPE, RSRTM20XX_ATTR_PROTOCOL_CAN_SEARCH_ID_TYPE, RSRTM20XX_ATTR_PROTOCOL_CAN_ID_TYPE Description changed ("Standard format", "") - CANIDType.B29 - RSRTM20XX_ATTR_PROTOCOL_CAN_TRIGGER_ID_TYPE, RSRTM20XX_ATTR_PROTOCOL_CAN_SEARCH_ID_TYPE, RSRTM20XX_ATTR_PROTOCOL_CAN_ID_TYPE Description changed ("Extended format", "") - CANIDType.Any - RSRTM20XX_ATTR_PROTOCOL_CAN_TRIGGER_ID_TYPE, RSRTM20XX_ATTR_PROTOCOL_CAN_SEARCH_ID_TYPE, RSRTM20XX_ATTR_PROTOCOL_CAN_ID_TYPE Description changed ("Any", "") - CANSearchFrameSetup.Sof - RSRTM20XX_ATTR_PROTOCOL_CAN_SEARCH_FRAME_SETUP Description changed ("Start of Frame", "")

RsRtm20xx Instrument Driver		
Driver history for C#, Visual Basic .NET		
Revision	Date	Note
		<ul style="list-style-type: none"> - CANSearchFrameSetup.Eof - RSRTM20XX_ATTR_PROTOCOL_CAN_SEARCH_FRAME_SETUP Description changed ("End of Frame", "") - CANSearchFrameSetup.Overload - RSRTM20XX_ATTR_PROTOCOL_CAN_SEARCH_FRAME_SETUP Description changed ("Overload Frame", "") - CANSearchFrameSetup.Error - RSRTM20XX_ATTR_PROTOCOL_CAN_SEARCH_FRAME_SETUP Description changed ("Error Frame", "") - CANSearchFrameSetup.Data11b - RSRTM20XX_ATTR_PROTOCOL_CAN_SEARCH_FRAME_SETUP Description changed ("Data11b", "") - CANSearchFrameSetup.Data29b - RSRTM20XX_ATTR_PROTOCOL_CAN_SEARCH_FRAME_SETUP Description changed ("Data29b", "") - CANSearchFrameSetup.Remote11b - RSRTM20XX_ATTR_PROTOCOL_CAN_SEARCH_FRAME_SETUP Description changed ("Remote11b", "") - CANSearchFrameSetup.Remote29b - RSRTM20XX_ATTR_PROTOCOL_CAN_SEARCH_FRAME_SETUP Description changed ("Remote29b", "") - CANSearchFrameType.Data - RSRTM20XX_ATTR_PROTOCOL_CAN_SEARCH_FRAME_TYPE Description changed ("Data", "") - CANSearchFrameType.Remote - RSRTM20XX_ATTR_PROTOCOL_CAN_SEARCH_FRAME_TYPE Description changed ("Remote", "") - CANSearchFrameType.Any - RSRTM20XX_ATTR_PROTOCOL_CAN_SEARCH_FRAME_TYPE Description changed ("Any", "") - LINPolarity.LowActive - RSRTM20XX_ATTR_PROTOCOL_LIN_POLARITY Description changed ("Low active", "") - LINPolarity.HighActive - RSRTM20XX_ATTR_PROTOCOL_LIN_POLARITY Description changed ("High active", "") - SPIMISOPolarity.LowActive - RSRTM20XX_ATTR_PROTOCOL_AUDIO_DATA_POLARITY Description changed ("Low active", "") - SPIMISOPolarity.HighActive - RSRTM20XX_ATTR_PROTOCOL_AUDIO_DATA_POLARITY Description changed ("High active", "") - DigitalHysteresis.Maximum - RSRTM20XX_ATTR_DIGITAL_HYSTERESIS Description changed ("Maximum", "") - DigitalHysteresis.Robust - RSRTM20XX_ATTR_DIGITAL_HYSTERESIS Description changed ("Robust", "") - DigitalHysteresis.Normal - RSRTM20XX_ATTR_DIGITAL_HYSTERESIS Description changed ("Normal", "") - TriggerHoldoffMode.Time - RSRTM20XX_ATTR_TRIGGER_HOLDOFF_MODE Description changed ("Time", "") - TriggerHoldoffMode.Off - RSRTM20XX_ATTR_TRIGGER_HOLDOFF_MODE Description changed ("Off", "") - PatternMode.Off - RSRTM20XX_ATTR_TRIGGER_PATTERN_MODE Description changed ("Off", "") - PatternMode.Timeout - RSRTM20XX_ATTR_TRIGGER_PATTERN_MODE

RsRtm20xx Instrument Driver		
Driver history for C#, Visual Basic .NET		
Revision	Date	Note
		<p>Description changed ("Timeout", "")</p> <p>- PatternMode.Width - RSRTM20XX_ATTR_TRIGGER_PATTERN_MODE Description changed ("Width", "")</p> <p>- TriggerOutMode.Off - RSRTM20XX_ATTR_TRIGGER_OUT_MODE Description changed ("Off", "")</p> <p>- TriggerOutMode.Trigger - RSRTM20XX_ATTR_TRIGGER_OUT_MODE Description changed ("Trigger", "")</p> <p>- TriggerOutMode.Mask - RSRTM20XX_ATTR_TRIGGER_OUT_MODE Description changed ("Mask", "")</p> <p>- DigitalTechnology.TTL - RSRTM20XX_ATTR_DIGITAL_TECHNOLOGY Description changed ("TTL", "")</p> <p>- DigitalTechnology.ECL - RSRTM20XX_ATTR_DIGITAL_TECHNOLOGY Description changed ("ECL", "")</p> <p>- DigitalTechnology.CMOS - RSRTM20XX_ATTR_DIGITAL_TECHNOLOGY Description changed ("CMOS", "")</p> <p>- DigitalTechnology.Manual - RSRTM20XX_ATTR_DIGITAL_TECHNOLOGY Description changed ("Manual", "")</p> <p>- ParallelBusFrameEnabled.Ok - RSRTM20XX_ATTR_PARALLEL_BUS_FRAME_ENABLED, RSRTM20XX_ATTR_PARALLEL_BUS_CLOCKED_FRAME_ENABLED Description changed ("Ok", "")</p> <p>- ParallelBusFrameEnabled.Error - RSRTM20XX_ATTR_PARALLEL_BUS_FRAME_ENABLED, RSRTM20XX_ATTR_PARALLEL_BUS_CLOCKED_FRAME_ENABLED Description changed ("Error", "")</p> <p>- ParallelBusFrameEnabled.Insufficient - RSRTM20XX_ATTR_PARALLEL_BUS_FRAME_ENABLED, RSRTM20XX_ATTR_PARALLEL_BUS_CLOCKED_FRAME_ENABLED Description changed ("Insufficient", "")</p> <p>- I2CFrameTransferDirection.Incomplete - RSRTM20XX_ATTR_PROTOCOL_I2C_FRAME_TRANSFER_DIRECTION Description changed ("Incomplete", "")</p> <p>- I2CFrameTransferDirection.Read - RSRTM20XX_ATTR_PROTOCOL_I2C_FRAME_TRANSFER_DIRECTION Description changed ("Read", "")</p> <p>- I2CFrameTransferDirection.Write - RSRTM20XX_ATTR_PROTOCOL_I2C_FRAME_TRANSFER_DIRECTION Description changed ("Write", "")</p> <p>- I2CFrameTransferDirection.Either - RSRTM20XX_ATTR_PROTOCOL_I2C_FRAME_TRANSFER_DIRECTION Description changed ("Either", "")</p> <p>- I2CFrameTransferDirection.Undefined - RSRTM20XX_ATTR_PROTOCOL_I2C_FRAME_TRANSFER_DIRECTION Description changed ("Undefined", "")</p> <p>- FrameAddressLength.Bit7 - RSRTM20XX_ATTR_PROTOCOL_I2C_FRAME_ADDRESS_LENGTH Description changed ("7 Bit", "")</p>

RsRtm20xx Instrument Driver		
Driver history for C#, Visual Basic .NET		
Revision	Date	Note
		<ul style="list-style-type: none"> - FrameAddressLength.Bit10 - RSRTM20XX_ATTR_PROTOCOL_I2C_FRAME_ADDRESS_LENGTH Description changed ("10 Bit", "") - LINFrameStatus.Ok - RSRTM20XX_ATTR_PROTOCOL_LIN_FRAME_STATUS Description changed ("Ok", "") - LINFrameStatus.UART - RSRTM20XX_ATTR_PROTOCOL_LIN_FRAME_STATUS Description changed ("UART", "") - LINFrameStatus.Checksum - RSRTM20XX_ATTR_PROTOCOL_LIN_FRAME_STATUS Description changed ("Checksum", "") - LINFrameStatus.ProtocolError - RSRTM20XX_ATTR_PROTOCOL_LIN_FRAME_STATUS Description changed ("Protocol Error", "") - LINFrameStatus.SystemError - RSRTM20XX_ATTR_PROTOCOL_LIN_FRAME_STATUS Description changed ("System Error", "") - LINFrameStatus.Weakup - RSRTM20XX_ATTR_PROTOCOL_LIN_FRAME_STATUS Description changed ("Weakup", "") - LINFrameStatus.Insufficient - RSRTM20XX_ATTR_PROTOCOL_LIN_FRAME_STATUS Description changed ("Insufficient", "") - LINFrameStatus.Error - RSRTM20XX_ATTR_PROTOCOL_LIN_FRAME_STATUS Description changed ("Error", "") - LINFrameStatus.Lener - RSRTM20XX_ATTR_PROTOCOL_LIN_FRAME_STATUS Description changed ("Lener", "") - LINChecksum.Ok - RSRTM20XX_ATTR_PROTOCOL_LIN_FRAME_CHECKSUM_ENABLED, RSRTM20XX_ATTR_PROTOCOL_LIN_FRAME_SYNC_ENABLED Description changed ("Ok", "") - LINChecksum.Error - RSRTM20XX_ATTR_PROTOCOL_LIN_FRAME_CHECKSUM_ENABLED, RSRTM20XX_ATTR_PROTOCOL_LIN_FRAME_SYNC_ENABLED Description changed ("Error", "") - LINChecksum.Undefined - RSRTM20XX_ATTR_PROTOCOL_LIN_FRAME_CHECKSUM_ENABLED, RSRTM20XX_ATTR_PROTOCOL_LIN_FRAME_SYNC_ENABLED Description changed ("Undefined", "") - LINParity.Ok - RSRTM20XX_ATTR_PROTOCOL_LIN_FRAME_PARITY_ENABLED Description changed ("Ok", "") - LINParity.ParityError - RSRTM20XX_ATTR_PROTOCOL_LIN_FRAME_PARITY_ENABLED Description changed ("Parity Error", "") - LINParity.UnexpectedValue - RSRTM20XX_ATTR_PROTOCOL_LIN_FRAME_PARITY_ENABLED Description changed ("Unexpected Value", "") - LINParity.Insufficient - RSRTM20XX_ATTR_PROTOCOL_LIN_FRAME_PARITY_ENABLED Description changed ("Insufficient", "") - LINFrameVersion.V1X - RSRTM20XX_ATTR_PROTOCOL_LIN_FRAME_VERSION Description changed ("V1X", "") - LINFrameVersion.V2X - RSRTM20XX_ATTR_PROTOCOL_LIN_FRAME_VERSION Description changed ("V2X", "") - LINFrameVersion.Unknown - RSRTM20XX_ATTR_PROTOCOL_LIN_FRAME_VERSION

RsRtm20xx Instrument Driver		
Driver history for C#, Visual Basic .NET		
Revision	Date	Note
		<p>Description changed ("Unknown", "")</p> <p>- LINByteEnabled.Ok - RSRTM20XX_ATTR_PROTOCOL_LIN_BYTE_ENABLED</p> <p>Description changed ("Ok", "")</p> <p>- LINByteEnabled.Insufficient - RSRTM20XX_ATTR_PROTOCOL_LIN_BYTE_ENABLED</p> <p>Description changed ("Insufficient", "")</p> <p>- LINByteEnabled.UART - RSRTM20XX_ATTR_PROTOCOL_LIN_BYTE_ENABLED</p> <p>Description changed ("UART", "")</p> <p>- UARTWordEnabled.Ok - RSRTM20XX_ATTR_PROTOCOL_UART_RX_WORD_ENABLED, RSRTM20XX_ATTR_PROTOCOL_UART_TX_WORD_ENABLED</p> <p>Description changed ("Ok", "")</p> <p>- UARTWordEnabled.Frst - RSRTM20XX_ATTR_PROTOCOL_UART_RX_WORD_ENABLED, RSRTM20XX_ATTR_PROTOCOL_UART_TX_WORD_ENABLED</p> <p>Description changed ("Frst", "")</p> <p>- UARTWordEnabled.Fren - RSRTM20XX_ATTR_PROTOCOL_UART_RX_WORD_ENABLED, RSRTM20XX_ATTR_PROTOCOL_UART_TX_WORD_ENABLED</p> <p>Description changed ("Fren", "")</p> <p>- UARTWordEnabled.Frme - RSRTM20XX_ATTR_PROTOCOL_UART_RX_WORD_ENABLED, RSRTM20XX_ATTR_PROTOCOL_UART_TX_WORD_ENABLED</p> <p>Description changed ("Frme", "")</p> <p>- UARTWordEnabled.Ster - RSRTM20XX_ATTR_PROTOCOL_UART_RX_WORD_ENABLED, RSRTM20XX_ATTR_PROTOCOL_UART_TX_WORD_ENABLED</p> <p>Description changed ("Ster", "")</p> <p>- UARTWordEnabled.Sper - RSRTM20XX_ATTR_PROTOCOL_UART_RX_WORD_ENABLED, RSRTM20XX_ATTR_PROTOCOL_UART_TX_WORD_ENABLED</p> <p>Description changed ("Sper", "")</p> <p>- UARTWordEnabled.Prer - RSRTM20XX_ATTR_PROTOCOL_UART_RX_WORD_ENABLED, RSRTM20XX_ATTR_PROTOCOL_UART_TX_WORD_ENABLED</p> <p>Description changed ("Prer", "")</p> <p>- UARTWordEnabled.Insufficient - RSRTM20XX_ATTR_PROTOCOL_UART_RX_WORD_ENABLED, RSRTM20XX_ATTR_PROTOCOL_UART_TX_WORD_ENABLED</p> <p>Description changed ("Insufficient", "")</p> <p>- UARTWordEnabled.Break - RSRTM20XX_ATTR_PROTOCOL_UART_RX_WORD_ENABLED, RSRTM20XX_ATTR_PROTOCOL_UART_TX_WORD_ENABLED</p> <p>Description changed ("Break", "")</p> <p>- CANFrameType.Data - RSRTM20XX_ATTR_PROTOCOL_CAN_FRAME_TYPE</p> <p>Description changed ("Data", "")</p> <p>- CANFrameType.Remote - RSRTM20XX_ATTR_PROTOCOL_CAN_FRAME_TYPE</p> <p>Description changed ("Remote", "")</p> <p>- CANFrameType.Error - RSRTM20XX_ATTR_PROTOCOL_CAN_FRAME_TYPE</p> <p>Description changed ("Error", "")</p> <p>- CANFrameType.Overload - RSRTM20XX_ATTR_PROTOCOL_CAN_FRAME_TYPE</p> <p>Description changed ("Overload", "")</p> <p>- CANFrameStatus.Ok - RSRTM20XX_ATTR_PROTOCOL_CAN_FRAME_STATUS</p>

RsRtm20xx Instrument Driver		
Driver history for C#, Visual Basic .NET		
Revision	Date	Note
		<p>Description changed ("Ok", "")</p> <ul style="list-style-type: none"> - CANFrameStatus.BitStuffingError - RSRTM20XX_ATTR_PROTOCOL_CAN_FRAME_STATUS <p>Description changed ("Bit Stuffing Error", "")</p> <ul style="list-style-type: none"> - CANFrameStatus.WrongCRC - RSRTM20XX_ATTR_PROTOCOL_CAN_FRAME_STATUS <p>Description changed ("Wrong CRC", "")</p> <ul style="list-style-type: none"> - CANFrameStatus.WrongACK - RSRTM20XX_ATTR_PROTOCOL_CAN_FRAME_STATUS <p>Description changed ("Wrong ACK", "")</p> <ul style="list-style-type: none"> - CANFrameStatus.CRC - RSRTM20XX_ATTR_PROTOCOL_CAN_FRAME_STATUS <p>Description changed ("CRC", "")</p> <ul style="list-style-type: none"> - CANFrameStatus.WrongEnd - RSRTM20XX_ATTR_PROTOCOL_CAN_FRAME_STATUS <p>Description changed ("Wrong End of Frame", "")</p> <ul style="list-style-type: none"> - CANFrameStatus.AckMissing - RSRTM20XX_ATTR_PROTOCOL_CAN_FRAME_STATUS <p>Description changed ("Acknowledge Missing", "")</p> <ul style="list-style-type: none"> - CANFrameStatus.Insufficient - RSRTM20XX_ATTR_PROTOCOL_CAN_FRAME_STATUS <p>Description changed ("Insufficient", "")</p> <ul style="list-style-type: none"> - CANAckState.Ok - RSRTM20XX_ATTR_PROTOCOL_CAN_ACK_STATE, RSRTM20XX_ATTR_PROTOCOL_CAN_CHECKSUM_STATE, RSRTM20XX_ATTR_PROTOCOL_CAN_DATA_LENGTH_STATE, RSRTM20XX_ATTR_PROTOCOL_CAN_ID_STATE, RSRTM20XX_ATTR_PROTOCOL_CAN_BYTE_STATE <p>Description changed ("Ok", "")</p> <ul style="list-style-type: none"> - CANAckState.Undefined - RSRTM20XX_ATTR_PROTOCOL_CAN_ACK_STATE, RSRTM20XX_ATTR_PROTOCOL_CAN_CHECKSUM_STATE, RSRTM20XX_ATTR_PROTOCOL_CAN_DATA_LENGTH_STATE, RSRTM20XX_ATTR_PROTOCOL_CAN_ID_STATE, RSRTM20XX_ATTR_PROTOCOL_CAN_BYTE_STATE <p>Description changed ("Undefined", "")</p> <ul style="list-style-type: none"> - QuestionableRegister.None - <p>Description changed ("None", "")</p> <ul style="list-style-type: none"> - QuestionableRegister.ChannelOverload - <p>Description changed ("Channel Overload", "")</p> <ul style="list-style-type: none"> - QuestionableRegister.Limit - <p>Description changed ("Limit", "")</p> <ul style="list-style-type: none"> - QuestionableRegister.Mask - <p>Description changed ("Mask", "")</p> <ul style="list-style-type: none"> - RegisterPart.Condition - <p>Description changed ("Condition", "")</p> <ul style="list-style-type: none"> - RegisterPart.Enable - <p>Description changed ("Enable", "")</p> <ul style="list-style-type: none"> - RegisterPart.Event - <p>Description changed ("Event", "")</p> <ul style="list-style-type: none"> - RegisterPart.NegativeTransition - <p>Description changed ("Negative Transition", "")</p> <ul style="list-style-type: none"> - RegisterPart.PositiveTransition - <p>Description changed ("Positive Transition", "")</p>

RsRtm20xx Instrument Driver		
Driver history for C#, Visual Basic .NET		
Revision	Date	Note
		<ul style="list-style-type: none"> - MeasurementSource.None - Description changed ("None", "") - MeasurementSource.Ch1 - Description changed ("Channel 1", "") - MeasurementSource.Ch2 - Description changed ("Channel 2", "") - MeasurementSource.Ch3 - Description changed ("Channel 3", "") - MeasurementSource.Ch4 - Description changed ("Channel 4", "") - MeasurementSource.M1 - Description changed ("Math 1", "") - MeasurementSource.M2 - Description changed ("Math 2", "") - MeasurementSource.M3 - Description changed ("Math 3", "") - MeasurementSource.M4 - Description changed ("Math 4", "") - MeasurementSource.M5 - Description changed ("Math 5", "") - MeasurementSource.R1 - Description changed ("Reference 1", "") - MeasurementSource.R2 - Description changed ("Reference 2", "") - MeasurementSource.R3 - Description changed ("Reference 3", "") - MeasurementSource.R4 - Description changed ("Reference 4", "") - MeasurementSource.Trigger - Description changed ("Trigger", "") - MeasurementSource - New items: Spectrum, MinHold, MaxHold, Average - AudioVariant.InterICSound - RSRTM20XX_ATTR_PROTOCOL_AUDIO_VARIANT Description changed ("Inter-IC Sound", "") - AudioVariant.LeftJustified - RSRTM20XX_ATTR_PROTOCOL_AUDIO_VARIANT Description changed ("Left-justified", "") - AudioVariant.RightJustified - RSRTM20XX_ATTR_PROTOCOL_AUDIO_VARIANT Description changed ("Right-justified", "") - AudioVariant.TimeDivisionMultiplexed - RSRTM20XX_ATTR_PROTOCOL_AUDIO_VARIANT Description changed ("Time Division Multiplexed", "") - AudioTriggerType.Data - RSRTM20XX_ATTR_PROTOCOL_AUDIO_TRIGGER_TYPE

RsRtm20xx Instrument Driver		
Driver history for C#, Visual Basic .NET		
Revision	Date	Note
		<p>Description changed ("Data", "")</p> <ul style="list-style-type: none"> - AudioTriggerType.Window - RSRTM20XX_ATTR_PROTOCOL_AUDIO_TRIGGER_TYPE <p>Description changed ("Window", "")</p> <ul style="list-style-type: none"> - AudioTriggerType.WordSelect - RSRTM20XX_ATTR_PROTOCOL_AUDIO_TRIGGER_TYPE <p>Description changed ("Word Select", "")</p> <ul style="list-style-type: none"> - AudioTriggerType.ErrorCondition - RSRTM20XX_ATTR_PROTOCOL_AUDIO_TRIGGER_TYPE <p>Description changed ("Error Condition", "")</p> <ul style="list-style-type: none"> - AudioChannel.Any - <p>Description changed ("Any", "")</p> <ul style="list-style-type: none"> - AudioChannel.TDMChannel1 - <p>Description changed ("TDM Channel 1", "")</p> <ul style="list-style-type: none"> - AudioChannel.TDMChannel2 - <p>Description changed ("TDM Channel 2", "")</p> <ul style="list-style-type: none"> - AudioChannel.TDMChannel3 - <p>Description changed ("TDM Channel 3", "")</p> <ul style="list-style-type: none"> - AudioChannel.TDMChannel4 - <p>Description changed ("TDM Channel 4", "")</p> <ul style="list-style-type: none"> - AudioChannel.TDMChannel5 - <p>Description changed ("TDM Channel 5", "")</p> <ul style="list-style-type: none"> - AudioChannel.TDMChannel6 - <p>Description changed ("TDM Channel 6", "")</p> <ul style="list-style-type: none"> - AudioChannel.TDMChannel7 - <p>Description changed ("TDM Channel 7", "")</p> <ul style="list-style-type: none"> - AudioChannel.TDMChannel8 - <p>Description changed ("TDM Channel 8", "")</p> <ul style="list-style-type: none"> - AudioChannel.Left - <p>Description changed ("Left", "")</p> <ul style="list-style-type: none"> - AudioChannel.Right - <p>Description changed ("Right", "")</p> <ul style="list-style-type: none"> - AudioFrameStatus.OK - RSRTM20XX_ATTR_PROTOCOL_AUDIO_FRAME_STATUS, RSRTM20XX_ATTR_PROTOCOL_AUDIO_FRAME_LEFT_CHANNEL_STATUS, RSRTM20XX_ATTR_PROTOCOL_AUDIO_FRAME_RIGHT_CHANNEL_STATUS, RSRTM20XX_ATTR_PROTOCOL_AUDIO_FRAME_TDM_STATUS <p>Description changed ("OK", "")</p> <ul style="list-style-type: none"> - AudioFrameStatus.Error - RSRTM20XX_ATTR_PROTOCOL_AUDIO_FRAME_STATUS, RSRTM20XX_ATTR_PROTOCOL_AUDIO_FRAME_LEFT_CHANNEL_STATUS, RSRTM20XX_ATTR_PROTOCOL_AUDIO_FRAME_RIGHT_CHANNEL_STATUS, RSRTM20XX_ATTR_PROTOCOL_AUDIO_FRAME_TDM_STATUS <p>Description changed ("Error", "")</p> <ul style="list-style-type: none"> - AudioFrameStatus.Insufficient - RSRTM20XX_ATTR_PROTOCOL_AUDIO_FRAME_STATUS, RSRTM20XX_ATTR_PROTOCOL_AUDIO_FRAME_LEFT_CHANNEL_STATUS, RSRTM20XX_ATTR_PROTOCOL_AUDIO_FRAME_RIGHT_CHANNEL_STATUS, RSRTM20XX_ATTR_PROTOCOL_AUDIO_FRAME_TDM_STATUS

RsRtm20xx Instrument Driver		
Driver history for C#, Visual Basic .NET		
Revision	Date	Note
		Description changed ("Insufficient", "") - HardcopyCommandSet - RSRTM20XX_ATTR_HARDCOPY_COMMAND_SET New items: Deskjet - ProbeInputImpedance.FiftyOhm - RSRTM20XX_ATTR_PROBE_INPUT_IMPEDANCE Enum name changed ("FiftyOhm", "50Ohm") - ProbeInputImpedance.OneMOhm - RSRTM20XX_ATTR_PROBE_INPUT_IMPEDANCE Enum name changed ("OneMOhm", "1MOhm")
1.3.0.0	09/2014	* Support for RTM firmware 5.500 * New Subsystems - ARINC 429 - Safe Operating Are - Transient Analysis - Current Harmonics >> Frequency Results - Current Harmonics >> Total Harmonic Distortion Results - Power Analysis >> Report * New Functions/Attributes - RSRTM20XX_ATTR_AVERAGING_STATUS - RSRTM20XX_ATTR_DIGITAL_CURRENT_STATUS_MAXIMUM - RSRTM20XX_ATTR_DIGITAL_CURRENT_STATUS_MINIMUM - RSRTM20XX_ATTR_DISPLAY_SEND_MESSAGE - RSRTM20XX_ATTR_FFT_AVERAGING_STATUS - RSRTM20XX_ATTR_HARDCOPY_COMMAND_SET - RSRTM20XX_ATTR_HARDCOPY_INCLUDE_MENU_IN_SCREENSHOT - RSRTM20XX_ATTR_HISTORY_CHANNEL_ACQUISITION_RELATIVE_TIME - RSRTM20XX_ATTR_HISTORY_DIGITAL_ACQUISITION_RELATIVE_TIME - RSRTM20XX_ATTR_HISTORY_MATH_ACQUISITION_RELATIVE_TIME - RSRTM20XX_ATTR_HISTORY_PROTOCOL_ACQUISITION_RELATIVE_TIME - RSRTM20XX_ATTR_MILSTD_SEARCH_TRANSMISSION_TYPE - RSRTM20XX_ATTR_MILSTD_SEARCH_WORD_START - RSRTM20XX_ATTR_MILSTD_TRIGGER_TRANSMISSION_TYPE - RSRTM20XX_ATTR_POWER_CONSUMPTION_MEASUREMENT_ADD_REPORT - RSRTM20XX_ATTR_POWER_CURRENT_HARMONICS_MEASUREMENT_ADD_REPORT - RSRTM20XX_ATTR_POWER_CURRENT_HARMONICS_MEASUREMENT_FUNDAMENTAL_MIL - RSRTM20XX_ATTR_POWER_CURRENT_HARMONICS_MEASUREMENT_FUNDAMENTAL_RTC - RSRTM20XX_ATTR_POWER_CURRENT_HARMONICS_NUMBER_OF_MEASURED_HARMONICS - RSRTM20XX_ATTR_POWER_DYNAMIC_ON_RESISTANCE_MEASUREMENT_ADD_REPORT - RSRTM20XX_ATTR_POWER EFFICIENCY_MEASUREMENT_ADD_REPORT - RSRTM20XX_ATTR_POWER_INRUSH_CURRENT_MEASUREMENT_ADD_REPORT - RSRTM20XX_ATTR_POWER_MODULATION_MEASUREMENT_ADD_REPORT - RSRTM20XX_ATTR_POWER_ON_OFF_MEASUREMENT_ADD_REPORT - RSRTM20XX_ATTR_POWER_QUALITY_MEASUREMENT_ADD_REPORT

RsRtm20xx Instrument Driver		
Driver history for C#, Visual Basic .NET		
Revision	Date	Note
		<ul style="list-style-type: none"> - RSRTM20XX_ATTR_POWER_RIPPLE_MEASUREMENT_ADD_REPORT - RSRTM20XX_ATTR_POWER_SLEW_RATE_MEASUREMENT_ADD_REPORT - RSRTM20XX_ATTR_POWER_SPECTRUM_MEASUREMENT_ADD_REPORT - RSRTM20XX_ATTR_POWER_SWITCHINGLOSS_MEASUREMENT_ADD_REPORT - RSRTM20XX_ATTR_RUN_SINGLE_WAIT_FOR_OPC - RSRTM20XX_FUNC_HISTORY_CHANNEL_ACQUISITION_ABSOLUTE_TIME - RSRTM20XX_FUNC_HISTORY_CHANNEL_ACQUISITION_DATE - RSRTM20XX_FUNC_HISTORY_DIGITAL_ACQUISITION_ABSOLUTE_TIME - RSRTM20XX_FUNC_HISTORY_DIGITAL_ACQUISITION_DATE - RSRTM20XX_FUNC_HISTORY_MATH_ACQUISITION_ABSOLUTE_TIME - RSRTM20XX_FUNC_HISTORY_MATH_ACQUISITION_DATE - RSRTM20XX_FUNC_HISTORY_PROTOCOL_ACQUISITION_ABSOLUTE_TIME - RSRTM20XX_FUNC_HISTORY_PROTOCOL_ACQUISITION_DATE * Modified Functions/Attributes - RSRTM20XX_ATTR_POWER_ANALYSIS_TYPE - SOA - RSRTM20XX_ATTR_MILSTD_SEARCH_CONDITION - Command Data - RSRTM20XX_ATTR_POWER_CURRENT_HARMONICS_MEASUREMENT_STANDARD - MIL, RTC - RSRTM20XX_ATTR_PROTOCOL_DISPLAY_FORMAT - Octal - RSRTM20XX_ATTR_PROTOCOL_TYPE - Arinc 429
1.2.0.0	04/2014	<ul style="list-style-type: none"> * New Subsystems - MILSTD Protocol - MILSTD Trigger - MILSTD Search - Display >> History - Display >> Segmentation - Trigger >> Runt - Mask Data - Mask Data Conversion * New Functions/Attributes - RSRTM20XX_ATTR_CHANNEL_THRESHOLD_HYSTERESIS - RSRTM20XX_ATTR_ZOOM_SAMPLE_RATE * Modified Functions/Attributes - RSRTM20XX_ATTR_TRIGGER_TYPE_A - added Runt - RSRTM20XX_ATTR_SEARCH_SOURCE - added SBUS1..4 - RSRTM20XX_ATTR_PROTOCOL_TYPE - Added MILSTD
1.0.0.0	12/2013	Initial release

About Rohde & Schwarz

Rohde & Schwarz is an independent group of companies specializing in electronics. It is a leading supplier of solutions in the fields of test and measurement, broadcasting, radiomonitoring and radiolocation, as well as secure communications. Established more than 75 years ago, Rohde & Schwarz has a global presence and a dedicated service network in over 70 countries. Company headquarters are in Munich, Germany.

Environmental commitment

- Energy-efficient products
- Continuous improvement in environmental sustainability
- ISO 14001-certified environmental management system



Regional contact

Europe, Africa, Middle East

+49 89 4129 12345

customersupport@rohde-schwarz.com

North America

1-888-TEST-RSA (1-888-837-8772)

customer.support@rsa.rohde-schwarz.com

Latin America

+1-410-910-7988

customersupport.la@rohde-schwarz.com

Asia/Pacific

+65 65 13 04 88

customersupport.asia@rohde-schwarz.com

R&S® is a registered trademark of Rohde & Schwarz GmbH & Co. KG; Trade names are trademarks of the owners.

Rohde & Schwarz GmbH & Co. KG

Mühl Dorfstraße 15 | D - 81671 München

Phone + 49 89 4129 - 0 | Fax + 49 89 4129 - 13777

www.rohde-schwarz.com